

Video on Demand Practical Tutorial Product Documentation





Copyright Notice

©2013-2024 Tencent Cloud. All rights reserved.

Copyright in this document is exclusively owned by Tencent Cloud. You must not reproduce, modify, copy or distribute in any way, in whole or in part, the contents of this document without Tencent Cloud's the prior written consent.

Trademark Notice

🔗 Tencent Cloud

All trademarks associated with Tencent Cloud and its services are owned by Tencent Cloud Computing (Beijing) Company Limited and its affiliated companies. Trademarks of third parties referred to in this document are owned by their respective proprietors.

Service Statement

This document is intended to provide users with general information about Tencent Cloud's products and services only and does not form part of Tencent Cloud's terms and conditions. Tencent Cloud's products or services are subject to change. Specific products and services and the standards applicable to them are exclusively provided for in Tencent Cloud's applicable terms and conditions.

Contents

Practical Tutorial
Media Upload
How to Pull Network Media Files to VOD
How to Upload Video from Server
How to Upload Videos over the Web
How to Increase the Speed and Success Rate of Media File Upload
Smart Cold Storage of VOD Media Asset Files
Video Processing
How to Add Subtitles to a Video
How to Transcode Videos
How to Moderate Media Content
How to Add Complex Watermarks to Videos
Distribution and Playback
How to Use Key Hotlink Protection
How to Prevent Malicious Video Hosting
How to Receive Event Notification
How to Migrate Files from Origin Server to VOD
Live Recording
Recording to VOD and Processing Video
Live Streaming Time Shifting
How to Make VOD Videos Live Streaming-Like
Using VOD and WordPress to Build a Website
How to Pull from Custom Origin Servers
How to Use EdgeOne to Distribute Content in VOD

Practical Tutorial Media Upload How to Pull Network Media Files to VOD

Last updated : 2022-12-16 15:02:33

Overview

Introduction

This document describes how to pull an online video (provided in the form of URL) to VOD.

Fees

The code provided in this document is open-source and free of charge, but it may incur the following fees during use: Fees for purchasing a Tencent Cloud CVM instance to run the API request script. For more information, please see Instance Billing Modes.

VOD storage space will be taken up by uploaded videos via pulling. For more information, please see Video Storage Pricing.

Limits

The pull from URL feature provided by VOD has the following limits:

The URL should directly point to a video file but cannot be a link to a video website page.

If the URL has a timestamp for hotlink protection, please make sure that the hotlink protection limits (such as the validity period and number of allowed access requests) are favorable; otherwise, the access may fail.

URLs with referer hotlink protection enabled are not supported.

DASH (MPD file type) is unsupported.

If the pull object is an HLS (.m3u8 file type) file, the URIs of media segments (generally in .ts file type) should be relative paths without parameters.

Upload by Pull in Console

Step 1. Activate VOD

Activate the VOD service as instructed in Getting Started - Step 1.

Step 2. Create a pull task

Go to the upload page in the VOD console, select **Pull** as the upload method, click **Add a Row**, enter the URL of the video to be pulled (the test URL is used here as an example. Other configuration items are optional, which can be entered as needed), and click **Pull Video** in the bottom-left corner:

÷	Video Ma	nagement tes	st 🔻 St			User Guide Me
	Upload Method	O Local Upload	II			
	Upload Video	Supports formats including download. For details, see	g WMV, RM, MOV, MPEG, MP4, 3GP, I Upload by Pulling 🗹 .	LV, AVI, and RMVB for batch upload	; supports importing links to CSV o	r TXT files for pulling. Cli
		Video URL	Video Name	Thumbnail URL	Category	Operation
		Add a Row				

Note:

The time it takes to pull a video is directly proportional to the video file size. We recommend you use a small video (of dozens of megabytes in size) for the test to avoid long wait.

Step 3. View the pull result

After waiting for one or two minutes (subject to the video file size), you can see the pulled video on the Media Assets page.

← Create Polic	icy 😵 test 💌 Su	
Policy Name	test Max 20 characters; allows letters, digits, spaces and	
Target Storage Class	s STANDARD_IA 💌	
Filter	Time (i)	
	Media File Category 🚯	
	Upload Source (i)	
	✓ Playback-based	
	If a video is played back less than 300 time(s) within 30 opolicy will be triggered.	day(s), the STAND,
	Media File Type	
Confirm	Cancel	

Note:

If the browser is stuck at the media assets page during the pull process, you need to refresh the page to view the pulled video.

Calling TencentCloud API for Pull

Step 1. Prepare a CVM instance

The TencentCloud API request script needs to be executed on a CVM instance meeting the following requirements: Region: not limited.

Model: the minimum official configuration (1 CPU core and 1 GB memory) is sufficient.

Public network: a public IP is required, and the bandwidth should be at least 1 Mbps.

```
Operating system: official public image Ubuntu Server 16.04.1 LTS 64-bit Or Ubuntu Server
```

18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, please see Operation Guide -Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System, respectively.

Note:

If you do not have a CVM instance satisfying the above conditions, you can also run the script on another Linux (such as CentOS or Debian) or macOS server with public network access, but you need to modify certain commands in the script based on the operating system. Please search for the specific modification method by yourself.

Step 2. Get the API key

Your API key (i.e., SecretId and SecretKey) is required for TencentCloud API request. If you have not created an API key yet, please generate one as instructed in Root Account Access Key. If you have already created a key, please get it as instructed in the same document.

Step 3. Activate VOD

Activate the VOD service as instructed in Getting Started - Step 1.

Step 4. Initiate a pull task

Log in to the CVM instance prepared in step 1 as instructed in Logging into Linux Instance in Standard Login Method and enter and run the following command on the remote terminal:

ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

Please assign the corresponding values obtained in step 2 to SECRET_ID and SECRET_KEY in the command. This command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote terminal will print the following information:

```
[2020-07-15 17:40:13] Start installing pip3.
[2020-07-15 17:40:39] pip3 is successfully installed.
[2020-07-15 17:40:39] Start installing the TencentCloud API SDK for Python.
[2020-07-15 17:40:42] The TencentCloud API SDK for Python is successfully installed
[2020-07-15 17:40:42] Start configuring API parameters.
[2020-07-15 17:40:42] API parameter configuration is completed.
```

Run the pull_upload.py script to initiate upload:

ubuntu@VM-69-2-ubuntu:~\$ cd ~/vod-server-demo/pull_upload_api/; python3 pull_upload

Note:

Please replace the URL in the command with the actual address of the video to be pulled.

This command will initiate a PullUpload request to the specified URL and print the response similar to the following:

```
{"TaskId": "1400329073-PullUpload-4ea60158fc6f8e611bbfa750eb1fd0a9t0", "RequestId":
```

Step 5. View the pull result

After waiting for one or two minutes (subject to the video file size), you can see the pulled video on the Media Assets page.

Video Info		Video Status	Video Category 🔻
00:00:28	API-PullUpload ID: 5285890806967135776	⊘ Normal	Others

Note:

If the browser is stuck at the media assets page during the pull process, you need to refresh the page to view the pulled video.

How to Upload Video from Server

Last updated : 2021-05-13 10:10:39

Overview

Introduction

This document describes how to upload a video file on your local server to VOD.

Fees

The code provided in this document is open-source and free of charge, but it may incur the following fees during use: Fees for purchasing a Tencent Cloud CVM instance to run the upload script. For more information, please see Instance Billing Modes.

VOD storage space will be taken up by uploaded videos via pulling. For more information, please see Video Storage Pricing.

Uploading Video in CVM to VOD

Step 1. Prepare a CVM instance

The upload script needs to be executed on a CVM instance meeting the following requirements:

Region: not limited.

Model: the minimum official configuration (1 CPU core and 1 GB memory) is sufficient.

Public network: a public IP is required, and the bandwidth should be at least 1 Mbps.

Operating system: official public image Ubuntu Server 16.04.1 LTS 64-bit or Ubuntu Server 18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, please see Operation Guide -Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System, respectively.

Note:

If you do not have a CVM instance satisfying the above conditions, you can also run the script on another Linux (such as CentOS or Debian) or macOS server with public network access, but you need to modify certain commands in the script based on the operating system. Please search for the specific modification method by yourself.

Step 2. Activate VOD

Please activate the VOD service as instructed in Getting Started - Step 1.

Step 3. Get the API key

Your API key (i.e., SecretId and SecretKey) is required for video upload. If you have not created an API key yet, please generate one as instructed in Root Account Access Key. If you have already created a key, please get it as instructed in the same document.

Step 4. Download the code and install the SDK

Log in to the CVM instance prepared in step 1 as instructed in Logging into Linux Instance in Standard Login Method and enter and run the following command on the remote terminal:

ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

Please assign the corresponding values obtained in step 3 to SECRET_ID and SECRET_KEY in the command. This command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote terminal will print information similar to the following:

```
[2020-06-23 19:56:31] Start installing pip3.
[2020-06-23 19:56:34] pip3 is successfully installed.
[2020-06-23 19:56:34] Start installing the VOD upload SDK for Python.
[2020-06-23 19:56:36] The VOD upload SDK for Python is successfully installed.
[2020-06-23 19:56:36] Start configuring SDK parameters.
[2020-06-23 19:56:36] SDK parameter configuration is completed.
```

Step 5. Upload a video

Before initiating upload, you need to prepare a video file and a cover image (optional) on your CVM instance. If it is inconvenient for you to upload a video to the CVM instance, you can run the following command on the remote terminal to download the test video and cover onto the CVM instance:

ubuntu@VM-69-2-ubuntu:~\$ wget http://1400329073.vod2.myqcloud.com/d62d88a7vodtransc

Run the server.upload.py script to start uploading:

ubuntu@VM-69-2-ubuntu:~\$ cd ~/vod-server-demo/server_upload/; python3 server_upload

Note:

Please replace the paths of the video and cover image in the command with the actual file paths. Here, the cover image path parameter is optional, and if it is left empty, the uploaded video will have no cover.

This command will upload the tencent_cloud.mp4video to VOD and upload the tencent_cloud.jpgimage as its cover. After the upload is completed, the remote terminal will print information similar to the following:

{"CoverUrl": "http://1400329073.vod2.myqcloud.com/ff439affvodcq1400329073/8aa658d15



Note:

If you want to use your own video for test, we recommend you use a small video file (of several megabytes in size) to avoid taking too much time for upload due to insufficient CVM bandwidth.

Step 6. View the result

On the Video Management page in the console, you can see the uploaded video file and cover.

Code Interpretation

1. main() is the script entry.

2. Call parse_conf_file() and read the configuration information from the config.json file. The configuration items are as described below:

Field	Data Type	Description
secret_id	String	API key
secret_key	String	API key
procedure	String	Task flow name. The specified task flow will be automatically triggered after video upload is completed. It is empty by default
subappid	String	Whether to upload the video to a VOD subapplication

Note:

This demo supports only the procedure and subappid upload parameters. For the complete features, please see SDK for Python.

3. Get the local path of the video file to be uploaded and the path of the cover image (if any) from the command line parameters and call upload_media() to initiate upload:

```
if len(sys.argv) < 2:
    usage()
    return
video_path = sys.argv[1]
cover_path = sys.argv[2] if len(sys.argv) > 2 else ""
# Initiate upload
rsp = upload_media(configuration, video_path, cover_path)
```

4. In upload_media(), use the method provided by the SDK for Python to construct an upload instance client, set upload parameters in req, and initiate upload:



```
client = VodUploadClient(conf["secret_id"], conf["secret_key"])
req = VodUploadRequest()

req.MediaFilePath = video
if cover != "":
    req.CoverFilePath = cover
if conf["procedure"] != "":
    req.Procedure = conf["procedure"]
req.SubAppId = int(conf["subappid"])

rsp = client.upload("ap-guangzhou", req)
return rsp
```

Note:

The first parameter ("ap-guangzhou") in client.upload() is the access region of the upload instance rather than the storage region of the uploaded video. You can simply fix the parameter value as "ap-guangzhou". If you want to specify the storage region for uploaded videos, please set the req.StorageRegion parameter.

Other Features

The VOD SDK for upload from server supports other features such as setting the video name, category, and expiration time. For more information, please see the SDK development guide for the corresponding programming language:

Java C# PHP Python Go

How to Upload Videos over the Web

Last updated : 2022-12-16 15:12:27

Overview

Demo features

This demo shows you how to upload videos to VOD through the webpage. It builds two HTTP services based on SCF: The first service is used to receive a request from the browser to get the signature for upload from client, calculate the signature, and return it.

The second service uses VOD's web upload SDK to implement a page. You can access the page in a browser to upload local videos to VOD.

Architecture and process

The system mainly involves four components: browser, API Gateway, SCF, and VOD. Here, API Gateway and SCF are the deployment objects of this demo as shown below:



The main business process is as follows:

1. The browser requests SCF for an upload page.

2. You select a local video and click upload on the upload page, and the browser requests SCF for an upload signature.

3. The browser uses the upload signature to initiate an upload request to VOD and displays the upload result on the upload page after completion.

Note:

The SCF code in the demo is developed based on Python 3.6. SCF also supports other programming languages such as Python 2.7, Node.js, Go, PHP, and Java for your choice as needed. For more information, please see Development Guide.

Fees

The VOD web upload demo (including the webpage code and service backend code) provided in this document is open-source and free of charge, but it may incur the following fees during service building and use:

Fees for purchasing a Tencent Cloud CVM instance to run the service deployment script. For more information, please see Instance Billing Modes.



Fees for using the upload page and signature distribution service provided by SCF. For more information, please see Billing Mode and Free Tier.

Fees for using Tencent Cloud API Gateway to provide public network APIs for SCF. For more information, please see Billing Overview.

Fees for VOD storage of uploaded videos. For more information, please see Pay-as-You-Go (Postpaid Daily Billing Cycle).

Fees for VOD traffic consumed by video playback. For more information, please see Pay-as-You-Go (Postpaid Daily Billing Cycle).

Quick Deployment of Web Upload Demo

The web upload demo is deployed on SCF with a service entry provided by API Gateway. To make it easier for you to build services, we provide a quick deployment script as detailed below.

Step 1. Prepare a CVM instance

The deployment script needs to be executed on a CVM instance meeting the following requirements: Region: not limited.

Model: the minimum official configuration (1 CPU core and 1 GB memory) is sufficient.

Public network: a public IP is required, and the bandwidth should be at least 1 Mbps.

Operating system: official public image Ubuntu Server 16.04.1 LTS 64-bit or Ubuntu Server 18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, please see Operation Guide -Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System, respectively.

Note:

The web upload demo itself does not depend on CVM but only uses CVM to run the deployment script.

If you do not have a CVM instance satisfying the above conditions, you can also run the script on another Linux (such as CentOS or Debian) or macOS server with public network access, but you need to modify certain commands in the deployment script based on the operating system. Please search for the specific modification method by yourself.

Step 2. Activate VOD

Please activate the VOD service as instructed in Getting Started - Step 1.

Step 3. Get the API key and APPID

Your API key (i.e., SecretId and SecretKey) and APPID are required for deploying and running the web upload demo service.

If you have not created an API key yet, please generate one as instructed in Root Account Access Key. If you have already created a key, please get it as instructed in the same document.

You can view the APPID on the Account Information page in the console.

Step 4. Deploy the service backend and webpage

Log in to the CVM instance prepared in step 1 as instructed in Logging In to Linux Instance in Standard Login Method and enter and run the following command on the remote terminal:

ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

Please assign the corresponding values obtained in step 3 to SECRET_ID, SECRET_KEY, and APPID in the command.

This command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote terminal will print the following information:

```
[2020-04-25 23:03:20] Start installing pip3.
[2020-04-25 23:03:23] pip3 is successfully installed.
[2020-04-25 23:03:23] Start installing Tencent Cloud SCF.
[2020-04-25 23:03:26] SCF is successfully installed.
[2020-04-25 23:03:26] Start configuring SCF.
[2020-04-25 23:03:28] SCF configuration is completed.
[2020-04-25 23:03:28] Start deploying the VOD client upload client signature distri
[2020-04-25 23:03:40] The deployment of the VOD client upload signature distributio
[2020-04-25 23:03:44] Start deploying the VOD web upload page.
[2020-04-25 23:03:53] The deployment of the VOD web upload page is completed.
[2020-04-25 23:03:53] Please access the following address in your browser to use th
```

Copy the address of the webpage in the output log (which is https://service-xxxxxx-

125xxxxxx.gz.apigw.tencentcs.com/release/web_upload_html in this example).

Note:

If the following warning is displayed in the output log, it is generally because the CVM instance cannot immediately parse the service domain name deployed just now. You can ignore this warning.

[2020-04-25 17:18:44] Warning: the client upload signature distribution service fai

Step 5. Use the web upload demo

- 1. Access the address copied in step 4 in a browser to start using the web upload demo.
- 2. Perform video upload operations on this page:
- 2.1 Select a local video file (MP4 format is recommended).
- 2.2 (Optional) Select a local cover image (in JPG or PNG format).
- 2.3 (Optional) Enter the video name.



2.4 Click Start Upload to upload the video.

3. After the upload is completed, the VOD media IDs (i.e., fileId) and URLs of the uploaded video and cover will

be displayed at the bottom of the page.

You can view the uploaded video in the VOD console.

Note:

You can try out other features on the upload page as prompted.

System Design Description

API protocol and test

Both the **upload page** and **upload signature distribution** functions use API Gateway to provide APIs. The specific API protocol is as detailed below:

Service	Function Name	API Form	Response Content
Upload page	web_upload_html	HTTP GET	HTML page
Upload signature distribution	ugc_upload_sign	HTTP POST	Upload signature

Upload page

You can access the SCF service list to view the details of the upload page service:

Note:

The two SCF functions used by the demo are deployed under the namespace vod_demo in the Guangzhou region. You need to select the corresponding region and namespace in the console to view the deployed SCF functions. Click the function name, select **Trigger Management** on the left, and **Access Path** on the right is the URL of the

upload page. Click API Service Name to redirect to the corresponding API Gateway page.

To test the service, directly access the page URL in a browser to check whether the upload page is displayed normally.

Upload signature distribution

You can access the SCF service list to view the details of the upload signature distribution service in the same way as detailed in Upload page.

Click the function name, select **Trigger Management** on the left, and **Access Path** on the right is the URL of the service. Click **API Service Name** to redirect to the corresponding API Gateway page.

To test the service, manually send an HTTP request and run the following command on a Linux or macOS device with public network access (please modify the service URL according to the actual situation):

curl -d '' https://service-xxxxxxx-125xxxxxx.gz.apigw.tencentcs.com/release/ugc_u

If the service is normal, an upload signature will be returned. Below is a sample signature:

VYapc9EYdoZLzGx0CglRW4N6kuhzZWNyZXRJZD1BS01EZk5xMz16dG5tYW1tVzBMOXFvZERia25hUjdZa0x

You can also use third-party tools such as Postman to send HTTP requests. Please search for specific usage on the internet.

Upload page service code interpretation

1. main_handler() is the entry function.

2. Read the content of the web_upload.html file, which is the upload page content.

```
html_file = open(HTML_FILE, encoding='utf-8')
html = html_file.read()
```

3. Read configuration items from config.json, which refer to the content that you cannot predict when you write the SCF service and need to determine during the deployment process. The content is written into config.json in real time by the deployment script before deploying the upload page service.

```
conf_file = open(CONF_FILE, encoding='utf-8')
conf = conf_file.read()
conf_json = json.loads(conf)
```

4. Call render_template and modify the upload page content according to the configuration information obtained in the previous step. The configuration items are expressed in the format of "variable name": "value" in the config.json file or in the format of {variable name} in the web_upload.html file.
When modifying them, please replace them with the specific values as detailed below.

```
def render_template(html, keys):
    """Replace the variables (in the format of `${variable name}`) in HTML with spec
    for key, value in keys.items():
        html = html.replace("${" + key + "}", value)
    return html
```

Variable	Description	Value Type	Value Source
UGC_UPLOAD_SIGN_SERVER	Upload signature distribution service URL	String	Output by SCF CLI after the deployment of the upload signature distribution service is completed.

5. Return the modified content of the upload page. For the formats and descriptions of the returned data, please see Overview of API Gateway Trigger.

```
return {
    "isBase64Encoded": False,
```

🕗 Tencent Cloud

}

```
"statusCode": 200,
"headers": {'Content-Type': 'text/html'},
"body": html
```

Upload signature distribution service code interpretation

1. main_handler() is the entry function.

```
2. Call parse_conf_file() and read the configuration information from the config.json file. The configuration items are as described below (for specific parameters, please see Signature for Upload from Client):
```

Field	Data Type	Description
secret_id	String	API key
secret_key	String	API key
sign_expire_time	Integer	Signature validity period in seconds
class_id	Integer	Category ID of the uploaded video. 0 indicates the default category
otp	Integer	Whether the signature is one-time
subappid	Integer	Whether to upload to a VOD subapplication

3. Call parse_source_context() to parse the sourceContext field in the request body, which can be passed through to the event notification receipt service during video upload completion event notification (not used in this demo).

Note:

This field is optional during the upload process. If you don't need this feature, you can ignore this part of the code.

4. Call the generate_sign() function to calculate the signature. For more information, please see Signature for Upload from Client.

5. Return the signature. For the formats and descriptions of the returned data, please see Overview of API Gateway Trigger.



How to Increase the Speed and Success Rate of Media File Upload

Last updated : 2021-10-28 14:38:10

Overview

No matter whether it is an upload from client or server, the following common quality problems may be encountered during file transfer:

1. Why is the file upload so slow?

- 2. How to speed up upload?
- 3. How to improve the upload success rate?
- 4. How to fix upload failures on mobile devices on weak networks?

The metrics that measure upload quality include upload speed and success rate.

The upload speed often affects the user experience in the most intuitive manner. For example, if users upload a video of 50 MB which is not completed after half an hour, they may lose patience, leading to the possibility of customer loss. The upload success rate is a guarantee of service quality. After the initial upload fails due to network problems, the possibility of initiating the upload again by the user will decrease. The immediate consequence will be user complaints. Therefore, ensuring high upload success rate is the most fundamental requirement.

This document describes the causes of and solutions to problems in VOD upload scenarios. You can make comparisons based on your actual business scenarios and choose appropriate solutions to improve the upload quality.

Things Affecting Upload Quality

Network bandwidth

Network bandwidth refers to the amount of data that can be transferred in a time unit. The higher the bandwidth, the greater the amount of data uploaded per time unit, and the faster the upload. Upload is an end-to-end activity, so the bandwidth at both ends has an impact on the upload quality. The backend servers of VOD currently have sufficient bandwidth, so the upload quality often depends on the user-side bandwidth.

Distance between user and storage center

The uploaded files eventually need to be stored in the storage center of VOD. After the user activates VOD, VOD will allocate **Chongqing** as the storage center by default. The distance between the user and the storage center affects the length of the network linkage.

For example, when a file is uploaded from Beijing to Chongqing, the linkage will be longer than that of uploading the same file from Chengdu to Chongqing, and the influencing factors will increase as the distance increases, eventually resulting in slower upload. Due to the long linkage, problems such as network jitter and packet loss during the transfer will also affect the upload success rate. For short linage, such problems may also occur, but their probability of occurrence is much lower than in long linkage. Shortening the distance between the user and the storage center is a key step in improving the upload quality.

Weak network

Weak network refers to the state of a network with high delay and packet loss rate, which is generally called "slow internet access". This problem is very common in real life, such as in elevators and subway trains. The main cause is poor reception in the affected environment, which results in slow or failing data packet transfer. This scenario is particularly common in uploads from client, especially in the current era of mobile internet. Weak network has been plaguing many developers as the most difficult issue to overcome in improving the upload success rate.

Solutions

Concurrent upload

For scenarios where network bandwidth is insufficient, a direct solution is to apply for more bandwidth. However, on a network with limited bandwidth, how to fully utilize the bandwidth for uploads is a problem that needs to be solved. Concurrent upload can be divided into two levels:

File level, i.e., multiple files are uploaded at the same time.

Part level, i.e., multiple parts of a single file are uploaded at the same time.

At both levels, the bandwidth utilization can be improved by adjusting the corresponding number of concurrencies.

Concurrent file upload

Concurrent file upload refers to using multiple processes or threads to initiate upload operations simultaneously. At present, VOD does not provide related SDK packages for this mode. You can implement this feature by referring to the characteristics of specific programming languages. Below is a simple example based on the VOD SDK for Java.

```
import com.qcloud.vod.VodUploadClient;
import com.qcloud.vod.model.VodUploadRequest;
import com.qcloud.vod.model.VodUploadResponse;
import java.util.ArrayList;
import java.util.List;
import java.util.concurrent.ExecutorService;
import java.util.concurrent.Executors;
public class Main {
```

```
public static void main(String[] args) throws Exception {
        // Number of concurrencies
        Integer threadNumber = 20;
        // List of paths to files to be uploaded
        List<String> filePathList = new ArrayList<String>();
        // Add paths to files to be uploaded
        filePathList.add("/data/path1.mp4");
        filePathList.add("/data/path2.mp4");
        filePathList.add("/data/path3.mp4");
        // Create a thread pool
        ExecutorService pool = Executors.newFixedThreadPool(threadNumber);
        // Create an upload client
        VodUploadClient client = new VodUploadClient("your secretId", "your secretK
        // Concurrent upload
        for (String path : filePathList) {
            // Submit an upload task
            pool.submit(new UploadThread(client, path));
        }
    }
}
// Upload thread
class UploadThread implements Runnable {
    // Upload client
    private VodUploadClient uploadClient;
    // File path
    private String filePath;
    public UploadThread(VodUploadClient uploadClient, String filePath) {
        this.uploadClient = uploadClient;
        this.filePath = filePath;
    }
    public void run() {
        VodUploadRequest request = new VodUploadRequest();
        request.setMediaFilePath(filePath);
        try {
            // Execute upload
            VodUploadResponse response = uploadClient.upload("ap-guangzhou", reques
            System.out.println(response.getFileId());
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
```

}

Concurrent part upload

Concurrent part upload is applicable to uploading a large file in multiple parts simultaneously. The advantage of multipart upload lies in that a large file can be uploaded quickly. The SDK provided by VOD automatically selects simple upload or multipart upload based on the file size, eliminating your need to take care of every step in multipart upload. The number of concurrent parts of the file is specified by the ConcurrentUploadNumber parameter. For specific use cases, please see the corresponding SDK. The SDKs that currently support this parameter include: SDK for Java

SDK for Python

SDK for Go

Nearby upload

Nearby upload refers to the ability to sense the location of the uploader and allocate the storage center closest to the uploader for file upload. For example, users in Chengdu will be allocated to the Chongqing rather than Shanghai region for upload.

The biggest benefit of the nearby upload capability is to shorten the transfer distance between the uploader and the server. This feature has the following advantages:

Shortened transfer distance and improved upload speed.

Improved stability and guaranteed success rate.

VOD natively supports nearby upload. You just need to simply confirm the following two points:

Activate multiple storage regions

The storage region provided by VOD is **Singapore** by default. If you want to take full advantage of the nearby upload capability, you need to activate regions desired for nearby upload in the console. For more information, please see Upload Storage Settings. After multi-region storage is enabled, when a user uploads a file, VOD will identify the user's region by IP and intelligently allocate the region closest to the user out of the activated regions for upload.

Check whether the scheduling is proper

If the storage regions of Chongqing and Shanghai are activated, and the user initiates an upload in Chengdu, the file will theoretically be uploaded to Chongqing through nearby scheduling. To confirm whether the scheduling is reasonable, you can get the FileId returned upon upload completion, and confirm it against the basic information (basicInfo) returned by the DescribeMediaInfos API, which contains a StorageRegion field representing the storage region of the uploaded media file.

If the transfer experiences proxy or forwarding, and the region identified by VOD by IP is incorrect, you can forcibly specify a storage region for file uploads. For specific directions, please see:

Guide for upload from client

Guide for upload from server

Pre-detection upload

Pre-detection upload is mainly a means to optimize various types of scenarios with network errors, such as network connection failure, timeout, and DNS hijacking. It is an effective mitigation solution offered by VOD for uploads on weak networks. The optimization strategy includes the following points:

HTTPDNS is used to resolve domain names and get backend addresses to prevent DNS hijacking.

The connectivity and upload speed in multiple regions are detected to determine the optimal upload target region.

Tencent Cloud CDN acceleration network is utilized to provide reliable and stable transfer tunnels.

The pre-detection upload capability is currently applied to uploads from client, and the connection method is simple. For specific directions, please see the description of pre-upload in the corresponding SDK:

Upload SDK for Android Upload SDK for iOS

©2013-2024 Tencent Cloud. All rights reserved.

Smart Cold Storage of VOD Media Asset Files

Last updated : 2022-05-26 12:13:36

Smart cold storage relies on the media asset management capabilities of VOD. To reduce the storage costs incurred when you use VOD, VOD enables media asset lifecycle management, with which you can change the storage class of VOD files from STANDARD to STANDARD_IA, ARCHIVE, or DEEP_ARCHIVE according to certain policies based on your business characteristics. In this way, you can manage your media asset files more flexibly.

Use Cases

Ecommerce live streaming: as stipulated by Measures for the Supervision and Administration of Online Trading issued by the State Administration for Market Regulation of China, live streaming service providers shall retain live streaming videos of online transactions for at least three years after the live streaming ends. Such videos are generally stored in VOD in STANDARD storage class, some of which will never or seldom be played back and will be only used for audit by applicable authorities. The smart cold storage feature can effectively help you reduce the storage costs of media assets.

Cold storage of infrequently accessed media: for video portals, streaming media platforms, and UGC management platforms, media assets that are infrequently accessed or watched by users cannot be directly removed for certain reasons, which incur high storage costs. The smart cold storage feature of VOD can store media files in a cold storage class according to the number of accesses, which effectively reduces the storage costs of media assets while still allowing infrequent watches.

Media asset archive: in news, media, radio, and TV industries, some media asset files are highly sensitive to time and generally stored for a long period as historical materials and will be searched and watched in the future only when required. In such scenarios, you can change their storage class to ARCHIVE or DEEP_ARCHIVE to reduce the storage costs.

Prerequisites

- 1. You have signed up for and logged in to your Tencent Cloud account and completed identity verification.
- 2. You have activated the VOD service.
- 3. You have created relevant policies. For more information, see Media Asset Cold Storage.

Use Instructions

🔗 Tencent Cloud

To use the media asset cold storage feature, you should understand the concepts of storage class, data retrieval and retrieval mode, and policy management.

Storage class

VOD provides the following storage classes for storing your media asset files: STANDARD, STANDARD_IA, ARCHIVE, and DEEP_ARCHIVE. Their attributes are as detailed below:

Storage Class	STANDARD	STANDARD_IA	ARCHIVE	DEEP_ARCHIVE
Default in VOD	Yes	No	No	No
Storage costs	High	Medium	Low	Very low
Access performance	High	Low	Access not supported	Access not supported
Data retrieval fees	No	No	Yes	Yes
Supported regions	All	All	All	Beijing, Shanghai, and Chongqing

STANDARD is the default storage class in VOD. Live recording files as well as files generated in various upload methods or video processing tasks are stored in STANDARD by default.

Attribute	Ranking from High to Low
Storage costs	STANDARD > STANDARD_IA > ARCHIVE > DEEP_ARCHIVE
Access performance	STANDARD > STANDARD_IA

Note:

ARCHIVE and DEEP_ARCHIVE storage classes don't support direct access, and you should retrieve the data first before you can access it. VOD only allows you to retrieve data to **STANDARD**.

Access performance will affect video watch metrics such as **time to first frame (TTFF) and lag rate**; therefore, **we recommend you not change the storage class for frequently accessed businesses in the production environment**.

VOD allows you to change between storage classes as follows:

Source Storage Class	Target Storage Class
STANDARD	STANDARD_IA, ARCHIVE, and DEEP_ARCHIVE
STANDARD_IA	STANDARD, ARCHIVE, and DEEP_ARCHIVE
ARCHIVE	STANDARD

Video on Demand

DEEP_ARCHIVE

STANDARD

Note:

To switch ARCHIVE and DEEP_ARCHIVE to another storage class other than STANDARD, you should switch them to STANDARD first and then switch STANDARD to the target storage class.

The granularity of storage class change is FileId, that is, the storage classes of the original and video processing files are the same, and you cannot specify the storage class for part of the files under the FileId separately.

Data retrieval and retrieval mode

Data retrieval

After the storage class of a media asset is changed to the ARCHIVE or DEEP_ARCHIVE storage class, the file cannot be directly accessed, that is, operations such as video playback and processing initiation cannot be performed. If you want to access it, you can change its storage class as instructed in the previous section. However, sometimes you only want to access a media asset for a short period of time and still retain it in ARCHIVE or DEEP_ARCHIVE after access. In this case, the above method is not applicable. To meet such needs, VOD provides the data retrieval capabilities.

VOD supports two retrieval operations for media in ARCHIVE and DEEP_ARCHIVE: permanent retrieval and retrieval for specified period.

Operation on ARCHIVE/DEEP_ARCHIVE	Storage Class Change	Retrieval
Real-Timeness	Async	Async
Mode	Expedited/Standard/Bulk	Expedited/Standard/Bulk
Validity period	Permanent	Specified period
Copy generation	No	Yes

1. After retrieval, VOD will generate a copy for the media asset in STANDARD storage class.

2. A retrieval copy is valid for a specific number of days, within which the media asset can be accessed. Once expired, it will be automatically cleared, and then the media asset will become inaccessible.

3. Within the copy's validity period, additional STANDARD storage fees will be incurred.

4. Within the copy's validity period, the media asset cannot be retrieved again.

Retrieval mode

Storage class change and retrieval for ARCHIVE and DEEP_ARCHIVE have multiple modes, which have the same final effect but are different in speed and cost (i.e., retrieval fees).

	Retrieval Mode Tir	ime of Retrieval from ARCHIVE	Time of Retrieval from DEEP_ARCHIVE	
--	--------------------	-------------------------------	-------------------------------------	--



Expedited mode	5 minutes	Not supported
Standard mode	5 hours	24 hours
Bulk mode	12 hours	48 hours

Note:

A media asset (represented as one FileId) can contain many files in storage, such as original file, transcoded file, and screenshot file, each of which may have different actual retrieval completion time. VOD doesn't maintain the specific retrieval completion status of each file but takes the media asset as a whole to calculate its retrieval completion time based on the longest possible time uniformly. Before that time arrives, even if all files under the media asset are retrieved, the media asset will still be marked as not retrieved and be inaccessible.

As the time point when a media asset is marked as unretrieved will be after the actual retrieval time point, the available duration of the retrieved copy of the media asset will be shorter than the expected period. To ensure that the copy has a sufficient available duration, we recommend you add one more day to the validity period when retrieving a media asset from DEEP_ARCHIVE.

Policy management

To help you uniformly manage the lifecycle of a large number of media assets, VOD combines media asset information and media asset file playback statistics to offer the policy-based smart management system. The VOD backend executes management tasks every day and changes the storage class of media assets that meet the conditions of the specific policy.

Policy capabilities

Combined filtering

A policy allows you to specify a series of conditions to change the storage class of media assets that meet all conditions **at the same time**. The specific filter conditions are as detailed below:

Media asset type, such as video, audio, and image.

Media asset creation date, which offers the following options:

Files created before the specified date.

Files created after the specified date.

Files created between two specified dates.

Files created before a certain number of days (which dynamically changes with the current date).

Unlimited (that is, all media assets meet this condition).

Category ID. You can specify multiple category IDs or none (that is, all media assets meet this condition).

Media asset source type, including live recording, upload, video editing, and other. You can specify multiple source types or none (that is, all media assets meet this condition).

🔗 Tencent Cloud

Number of recent playbacks. You can filter media assets whose number of playbacks is less than the specified value in the specified number of days. You can also set no limit (that is, all media assets meet this condition).

Disabling policy

Once created, a policy will be started automatically, and you can disable it as needed. Once disabled, it will be ignored in management tasks created on the next day and afterwards until it is enabled again.

Note:

Once disabled, a policy may still take effect or not take effect in the management tasks on the current day.

Restrictions

Up to 10 policies can be configured.

You cannot specify the policy priority. If a media asset hits multiple policies at the same time, the policy priorities will be automatically determined by the target storage class as follows: DEEP_ARCHIVE > ARCHIVE > STANDARD_IA.

Configuring VOD Smart Cold Storage Policy

Step 1. Create a cold storage policy

Log in to the VOD console (non-admin), click **Media Assets** > **Cold Storage** on the left sidebar, and click **Create Policy**.

VOD	Cold Storage Prima	ry application 🔻	SubAppld:			
E Service Overview	Custom Rule-based	FileId-based				
■ Media Assets ^		You can set policies for	cold storage. For details, see Cold Storage.			
 Video Management 		You can create up to 10) cold storage policies in the VOD console.			
 Image Management 	[Create Policy				
Cold Storage		Policy ID/Name	Storage Type	Creation Time	Enabled/Disabled	Operation
Task Management		-	STANDARD_IA	2021-10-14 19:24:39		Edit Delete
Video Audit System Settings		Total items: 1				10 ¥ / page H 4 1 / 1 page > H

Step 2. Configure the cold storage policy

← Create Policy	📚 test 💌 Si			User Guide 🛛 Cold Storage 🖾
Policy Name	test			
	Max 20 characters; allows letters, digits, spaces and			
Target Storage Class	STANDARD_IA 👻			
Filter	Time (i)			
	Media File Category (i)			
	Upload Source 🚯			
	✓ Playback-based			
	If a video is played back less than 300	time(s) within	30	day(s), the STANDARD_IA storage
	policy will be triggered.			
	Media File Type			
Confirm	ancel			

Configure the cold storage policy as needed.

Example: as shown above, if the number of video playbacks is less than 300 in 30 days for a video, the STANDARD_IA storage policy will be triggered, and VOD will store all media assets meeting the rule in STANDARD_IA.

Step 3. Confirm the configuration for it to take effect

VOD	← Crea	ate Policy	Primary application	 Cold Storage 🔝	1
B Service Overview				y created successfully. 🗙	1
Media Assets ^			\odot		
 Video Management 			Created successfully. Not can click the bettom below to go to the Cold Storage page to enable this policy for applicable VOD media files. Enable Adv.		
 Image Management 					
Cold Storage					

Video Processing How to Add Subtitles to a Video

Last updated : 2024-11-11 16:28:30

VOD supports adding (or deleting) standard multilingual subtitle files to HLS videos outputted from Adaptive Bitrate Streaming. During playback, users can switch between different language subtitles to enhance the viewing experience.

The process includes two steps: **Add subtitles to the media files** and **Associate subtitles with the media files**. For ease of description, this article assumes the following specific scenario: add Chinese (zh) and English (en) subtitles to the output file from the adaptive streaming template ID (10) for FileId (1397757888586312345), so that when playing the file, you can choose to display the added Chinese or English subtitles.

Step 1. Add Subtitles to Media Files

This step adds subtitles to the media asset with FileId (1397757888586312345) and obtains a subtitle ID. Next, this subtitle ID will be used for subtitle association.

VOD provides two ways to add subtitles to media files: uploading subtitles and automatic subtitle generation.

Upload Subtitles

Upload existing subtitle files. After a successful upload, the subtitle information is automatically added to the media asset. There are two upload methods: console upload and server API upload.

Upload through console

1. log in to VOD console, go to the audio and video management page of the target application, and click **manage** the media asset you need to process.

← Application	Audio/Video Management S Primary application ~
Management	Uploaded Uploading
Application Overview	
▶ Video/Audio ∧ Management	 To view the status of your media processing tasks, go to <u>Task Center</u>. The status on this page indicates whether a file is blocked. Blocking takes effect in about five minutes. Blocked files cannot be played. The VOD console shows at most 5,000 media files. You can <u>export</u> the information of all your media files. The files you upload to VOD will incur storage costs, which vary according to the storage class you choose. Fees incurred each day are deducted the following day. For the usage and billing details, see your billing states.
 Audio/Video Management 	Upload Video Transcoding Scenario transcoding Adaptive bitrate streaming Task Flow Content moderation Remaster Separate key w
 Image Management 	Intelligent Recognition
Cold Storage	Name/ID Status Moderation result Source Y Uploading time ‡ Expiration time() Storage Type
Smart Bitrate NEW Reduction	Ormal Verified Upload Permanent STANDARD
Task center	
System Configuration	Not moderated yet Upload Permanent STANDARD

2. Click Subtitle > Add Subtitles.

Transcoding outputs	Screenshots Subtitles Well	o player code
 'Note: The subtitle function <u>Videos</u>'. 	on requires associating with adaptive streaming. Ple	ease associate with the specified adaptive streaming after upload
Subtitles 2 Add subtitles Inte	ligent Recognition Batch delete subtities	
Subtitle ID	Source	Language Stre
		You haven't added any su
Associated adaptive bits	tream	



3. Upload the required subtitle file, and edit **language** and **stream name** (for display in the player), then click **Confirm.**

Add subtitles				
The subtitles m After uploading	ust be in VTT format. I a subtitle file, you nee	d to bind it to a stream.		
Upload subtitles	Select File Up	bload a VTT file. Each file ID can h	ave up to 16 subtitle files.	
0	File Name	Language	Stream name	Format
	demo_cn.vtt	Chinese ~	demo_cn.vtt	VIT
	demo_en.vtt	English ~	demo_en.vtt	VIT
		2 Confirm	Off	

4. The Chinese and English subtitle IDs are qFXJrv and PPGQep, respectively.

Subtitles Add subtitles	Intelligent Recognition Batch delete subtities			
Subtitle ID	Source	Language	Stream name	Format
qFXJrv	Upload	Chinese	demo_cn.vtt	VTT
PPGQep	Upload	English	demo_en.vtt	VTT

Server API Upload

1. Invoke the server API ModifyMediaInfo, input parameters AddSubtitles to specify the subtitles to be uploaded:

```
"Language": "zh",
    "Format": "vtt",
    "Content": "V0VCV1RUCgowMDowMC4wMDAgLS0+IDAwOjAwOjAyLjA0MArkvaDlpb3lkJf
},
{
    "Name": "demo_en.vtt",
    "Language": "en",
    "Format": "vtt",
    "Content": "vtt",
    "Content": "V0VCV1RUCgowMDowMC4wMDAgLS0+IDAwOjAwOjAyLjA0MApIb3cgYXJ1IH1
}
```

2. Example of interface output (other fields omitted), from which the Chinese and English subtitle IDs are qFXJrv and PPGQep, respectively.

```
{
    "Response": {
        "AddedSubtitleSet": [
            {
                "Id": "qFXJrv",
                "Name": "demo_cn",
                "Language": "en",
                "Format": "vtt",
                "Url": "http://123.vod2.myqcloud.com/vodgzp123/1397757888586312345/
            },
            {
                "Id": "PPGQep",
                "Name": "demo_en",
                "Language": "en",
                "Format": "vtt",
                "Url": "http://123.vod2.myqcloud.com/vodqzp123/1397757888586312345/
            }
        ],
        "RequestId": "90b40581-bf44-4455-a238-c8fe614c20ca"
    }
}
```

Intelligent Recognition Subtitle Generation

Through Audio and Video CR, automatically generate subtitles and add subtitle information to media assets. The process includes: preparing Audio and Video CR Templates, Task Initiation, and Result Acquisition. The key points are as follows:

1. Preparing Audio and Video CR Templates

There are two ways to create templates: console creation and server API creation.



1.1. Console Creation of Templates

1.1.1. Log in to VOD Console, after entering the target application, click **Media Processing > Template Settings >** Intelligent Recognition Template, click Create Intelligent Recognition Template.

Application Management Application Overview 2	Template Settings Video Transcoding Intelligent Recognitio	 Primary application Scenario transcoding template on Template 	SubAppld: 1329083957 g Audio Transcoding Re	mux Adaptive Bitrate S	treaming Image processing	Watermark Sc
Video/Audio Management	3	Using media processing funct Create Intelligent Recognition Te	tions will incur corresponding fees.	For details, please refer toMedi	a processing	
System Configuration		Template Name/ID AsrFullText-Chinese	Content Recognition Item Speech to Text	Output File	Creation Time 2024-10-22 10:20:00	Update Time 2024-10-23 14:28
Template Settings Task Flow Settings		AsrFulText-English	Speech to Text	vtt	2024-10-22 10:20:01	2024-10-23 14:35
 Commercial- grade DRM 		AsrFullText-Japanese	Speech to Text	vtt	2024-10-22 10:20:02	2024-10-23 14:47
Distribution and Playback Settings		AsrTranslate-Chinese_to_English	Speech Translation	vtt	2024-10-22 10:20:03	2024-10-23 14:52

1.1.2. Supports selecting "Speech to Text" to output the source language subtitle file, or "Speech Translation" to output the subtitle file in the target translation language. The following screenshot scenario describes converting source video speech to CR and translating it to the target language subtitle file.
Template Name	Please enter the template name
	Only supports Chinese, English, numbers, underscore (_), hyphen (-), and period (.) characters. The length should not
Content Reco	ognition Configuration
Speech to Text Speech Translat	Speech to Text Speech Translation 2
,	Video Source Language Simplified Chinese 🔻
	Translation Target Language Japanese 🔻
	Subtitle File Format
Confirm	Cancel

1.1.3. After creating, you can see the newly created template ID 72314 in the template list.

Create Intelligent Recognition Ten	nplate				
Template Name/ID	Content Recognition Item	Output File	Creation Time	Update Time	Template Type T
demo11 72314	Speech Translation	vtt	2024-11-01 15:45:11	2024-11-01 15:45:11	Custom

1.2. Create template via Server API

1.2.1. Invoke the server API to create an audio/video CR template. The input parameter AsrTranslateConfigure specifies the speech translation task parameters:

```
"AsrTranslateConfigure": {
    "Switch": "ON",
    "SrcLanguage": "zh",
    "DstLanguage": "en",
    "SubtitleFormats": ["vtt"]
}
```

Note, if subtitle translation is not needed, you can use Speech Full Text Recognition (AsrFullTextConfigure) to specify generating subtitles in the video source language:

```
"AsrFullTextConfigure": {
    "Switch": "ON",
    "SrcLanguage": "zh",
    "SubtitleFormats": ["vtt"]
}
```

1.2.2. According to this scenario, we specified Speech Translation (AsrTranslateConfigure). The interface output example (other fields omitted) provides the template ID (72314).

```
{
    "Response": {
        "Definition": 72314,
        "RequestId": "12ae8d8e-dce3-4151-9d4b-5594145287e1"
    }
}
```

2. Task Initiation

Multiple methods are supported to initiate intelligent recognition tasks:

Invoke server API

Initiate task flow from the console

Specify task flow upon upload

Upload from server

Upload from client

Upload through console

For the above methods, please refer to the Developer Guide Task Initiation. Additionally, you can directly initiate an II task through the console as follows:

2.1. Log in to VOD console, go to the Audio and Video Management page of the target application, select the FileId for subtitle generation, and click **Intelligent Recognition.**

← Application Management	Audio/Video Management Primary application
Application Overview	
► Video/Audio ∧ Management	 To view the status of your media processing tasks, go to <u>Task Center</u>. The status on this page indicates whether a file is blocked. Blocking takes effect in about five minutes. Blocked files cannot be plue The VOD console shows at most 5,000 media files. You can <u>export</u> the information of all your media files. The files you upload to VOD will incur storage costs, which vary according to the storage class you choose. Fees incurred each day are deducted the following day. For the usage and billing details, see
 Audio/Video Management 	Uplend Video Transcoding Scenario transcoding Adaptive bitrate streaming Task Flow Content moderation Bernaster
 Image Management 	Intelligent Recognition New More ~
Cold Storage	Name/ID Status Moderation result Source 🖓 Uploading time ‡ Expiration time)
Smart Bitrate NEW Reduction	IMG ID:1: iD:1:

2.2. Click Select template.



2.3. Select the recognition template you want to use and then click Confirm.

×

Select Intelligent Recognition Template

When the content recognition item is "Speech to Text," it automatically generates subtitle files by intelligently recognizing the audio in videos. When the content recognition item is "Speech Translation," it recognizes and translates into specified languages, generating multilingual subtitle files.

	Template name/ID	Content Recognition Item	Subtitle Format	Creation Time	Update Time	Template Type
	Malay_to_English 123	Translation	vtt	10:20:05	15:02:26	Preset
	AsrTranslate- English_to_Malay 124	Speech Translation	vtt	2024-10-22 10:20:06	2024-10-23 15:07:44	Preset
	AsrTranslate- Chinese_to_Japan ese 125	Speech Translation	vtt	2024-10-22 10:20:07	2024-10-23 15:12:52	Preset
	AsrTranslate- Chinese_to_Korea n 126	Speech Translation	vtt	2024-10-22 10:20:08	2024-10-23 15:18:08	Preset
0	1 ₀₁₁ 72314	Speech Translation	vtt	2024-11-01 15:45:11	2024-11-01 15:45:11	Custom
Tota	l items: 10			20 🗸 / page	₩ ◀ 1	/1 page 🕨 🕨
		2	Confirm	Cancel		

Processing Type	Video Transcoding	Scenario templates Adaptive bit	rate streaming Task Flow	Content moderation	emaster O Intelligent Recogniti	NEW ON
Intelligent Recognition *	Select template					
	Template name/ID	Content Recognition Item	Subtitle Format	Creation Time	Update Time	
	demo11 72314	Speech Translation	vtt	2024-11-01 15:45:11	2024-11-01 15:45:11	

The page will indicate that the task has been successfully created:



2.4. On the **Task Center** page, you can see the task ID and task status of the subtitle generation task.

	Application Overview	The Task Management page only displays the	ne details of executed tasks and only su	pports querying the ta	sk processing status and tas	sk details within last 72 hours.	
D	► Video/Audio Management	File ID V Search tasks by file ID	Q				
	Task center	Task ID	File ID	Task Type	Task Status	Creation Time ‡	Completion Time \$
s	system Configuration		ъ 5 Ф	Process Video	 Completed 		
2	👌 Media Processing 🛛 🗸						
5	Distribution and						

When the task status shows Completed, the subtitles have been successfully generated and automatically added to the media assets.

3. Result Acquisition

Tencent Cloud

Using the task ID obtained from Back 'Task Initiation' and following the development guide Result Acquisition, you can obtain the subtitle generation results, which are located in the AiRecognitionResultSet array (type AiRecognitionResult) within the ProcedureTask structure:

When Type is AsrFullTextRecognition, it indicates that the full text translation result is saved in AsrFullTextTask. When Type is AsrTranslateRecognition, it indicates that the translation result is saved in AsrTranslateTask. Example of AsrTranslateTask:

```
{
    "Status": "SUCCESS",
    "ErrCode": 0,
    "ErrCodeExt": "",
    "Message": "SUCCESS",
    "Progress": 100,
    "BeginProcessTime": "2024-10-16T12:21:04Z",
    "FinishTime": "2024-10-16T12:21:47Z",
    "Input": {
        "Definition": 102270
    },
    "Output": {
        "SegmentSet": [
    }
}
```

```
"Text": "How are you?",
            "Translation": "How are you?",
            "StartTimeOffset": 0,
            "EndTimeOffset": 2.04,
            "Confidence": 100
        },
        {
            "Text": "I am good, thank you. How about you?",
            "Translation": "Fine, thank you, and you?",
            "StartTimeOffset": 2.1,
            "EndTimeOffset": 4.95,
            "Confidence": 100
        },
        {
            "Text": "I am good too.",
            "Translation": "I'm fine too.",
            "StartTimeOffset": 4.98,
            "EndTimeOffset": 6.9,
            "Confidence": 100
        }
    ],
    "SegmentSetFileUrl": "http://251000800.vod2.myqcloud.com/6c0f30dfvodgzp2510
    "SegmentSetFileUrlExpireTime": "2024-10-19T12:21:44.525Z",
    "SubtitleSet": [
        {
            "Id": "qFXJrv",
            "Name": "zh",
            "Language": "zh",
            "Format": "vtt",
            "Url": "https://123.vod-qcloud.com/vodgzp123/1397757888586312345/su
        },
        {
            "Id": "PPGQep",
            "Name": "en",
            "Language": "en",
            "Format": "vtt",
            "Url": "https://123.vod-qcloud.com/vodgzp123/1397757888586312345/su
        }
   ]
}
```

The example above shows that the Chinese and English subtitle IDs are qFXJrv and PPGQep, respectively. When the task is successful, the generated subtitle information has been automatically added to the media assets.

}

Step 2. Associate subtitles with the media files

There are two ways to associate subtitles with the media files: associating subtitles via the console and associating subtitles via server APIs. The former only supports associating subtitles with already generated Adaptive Bitrate output files, while the latter supports associating subtitles with both stock and incremental files.

Console Subtitle Association

1. log in to VOD console, go to the audio and video management page of the target application. Click **Manage** > **Subtitles** > **Edit** for the Media Asset with FileId (1397757888586312345).

Transcoding outputs S	creenshots Subtitles Web pl	ayer code			
 'Note: The subtitle function requi <u>Videos</u>'. 	res associating with adaptive streaming. Please	associate with the specified adaptive strea	aming after uploading or obtaining the subt	itle file through intelligent recognition. For	r more details, refer to ' <u>How to Add Subtitles to</u>
Subtitles	NEW				
Add subtilles Intelligent H	Source	Language	Stream name	Format	Operation
qFXJrv	Upload	Chinese	demo_cn.vtt	VIT	Delete
PPGQep	Upload	English	demo_en.vtt	VTT	Delete
					Delete
Associated adaptive bitstream					
Adaptive oltrate streaming	Protocol	Association Sta	tus Dat	ault subtities	Operation
Adpative-HLS 10	HLS	Not associated	Nor	ne	Edit

Suppo specify	rts multiple subtitle file selec ying 'default subtitles', auton	tion, and can switch to different natically turning on subtitles durin	languages for subtitle display durir ng playback, and displaying defaul	ng playback. Supports t subtitle content.
	Subtitle ID	Language	Stream name	Operation
	qFXJrv	Chinese	demo_cn.vtt	Set as default
	PPGQep	English	demo_en.vtt	Set as default
	1000			

2. After clicking **Confirm**, an Operation Successful prompt will pop up in the upper right corner of the page, indicating that the subtitle association was successful.

Server API Associated Subtitles

Including associating subtitles with existing files and incremental files.

1. Associating subtitles with existing files

To associate subtitles with the output files of adaptive bitrate conversion, please invoke the server API Associated Media Subtitles. Input parameters are as follows:

```
{
    "Action": "AttachMediaSubtitles",
    "Version": "2018-07-17",
    "FileId": "1397757888586312345",
    "Operation": "Attach",
    "AdaptiveDynamicStreamingDefinition": 10,
    "SubtitleIds": ["qFXJrv", "PPGQep"]
}
```

2. Associating subtitles with incremental files

When initiating an Adaptive Bitrate Streaming task, specify the subtitle ID list in the input parameters of the Adaptive Bitrate Streaming task: MediaProcessTask -> AdaptiveDynamicStreamingTaskSet -> SubtitleSet . The input parameter example for MediaProcessTask is as follows:

```
{
    "AdaptiveDynamicStreamingTaskSet": [
        {
          "Definition": 10,
          "SubtitleSet": ["qFXJrv", "PPGQep"]
        }
    ]
}
```

Once the task is completed, the output file of the adaptive bitrate streaming will be associated with subtitles.

Step 3. Playback Effect

After successfully associating subtitles, you can choose to display subtitles in different languages while playing the video. Refer to the effect in the image below:



How to Transcode Videos

Last updated : 2023-05-15 17:39:49

Instructions

Overview

This document describes how to transcode videos stored in VOD and how to get the outputs.

Costs

The open-source code provided in this document is free, but the following costs may incur.

Fees for purchasing a Tencent Cloud CVM instance to execute TencentCloud API requests. For more information, see CVM Billing Mode.

Fees for storing videos in VOD. For details, see Pay-As-You-Go and Prepaid Packages.

Fees for transcoding videos stored in VOD. For details, see Pay-As-You-Go and Prepaid Packages.

Fees for playing videos stored in VOD. For details, see Pay-As-You-Go and Prepaid Packages.

Parameters

VOD supports the following formats for transcoding:

Туре	Parameter	Description
Input	Container format	WMV, RM, MOV, MPEG, MP4, 3GP, FLV, AVI, RMVB, TS, ASF, MPG, WEBM, MKV, M3U8, WM, ASX, RAM, MPE, VOB, DAT, MP4V, M4V, F4V, MXF, QT, and OGG.
	Video codec	AV1, AVS2, H.264/AVC, H.263, H.263+, H.265, MPEG-1, MPEG-2, MPEG-4, MJPEG, VP8, VP9, QuickTime, RealVideo, Windows Media Video
		Video: FLV, MP4, HLS (M3U8 + TS)
Output	Container format	Audio: MP3, MP4, Ogg, FLAC, M4A
Output		Image: GIF, WebP.
	Video codec	H.264/AVC, H.265/HEVC, AV1

The target specifications of a transcoding task include codec, resolution, bitrate, and others. VOD uses templates to represent different combinations of these parameters. For details, see Video Processing - Overview.

Category	Parameter	Description

Video encoding	Codec	H.264, H.265, and AV1 codecs are supported.
encoding	Bitrate	Supported bitrate range: 10 Kbps - 35 Mbps.
	Frame rate	Supported frame rate range: 1-60 fps; common values: 24, 25, and 30.
	Resolution	Supported width range: 128 px - 4096 px. Supported height range: 128 px - 4096 px.
	GOP length	Supported GOP length range: 1-10s
	Profile	When the video codec is H.264, the baseline, main, and high profiles are supported. When the video codec is H.265, only the main profile is supported.
	Color space	YUV420p is supported.

Note:

Codec: A method of converting video files from a certain format into another using specific compression technology. Compared with H.264, H.265 uses more advanced encoding techniques and can transcode videos at much lower bitrates (which means lower bandwidth costs) without compromising video quality.

Bitrate: The size of data encoded by the encoder per second, in kbps. For example, 800 kbps indicates that the encoder generates 800 KB of data per second.

Frame rate: The number of frames per second.

Resolution: The number of pixels per inch.

GOP: The number of frames between two I-frames.

For general transcoding, we recommend the following resolution and bitrate combinations:

Definition	Recommended Bitrate	Recommended Resolution	Resolution Range
SD	600	640 x 480	SD (short side \leq 480 px)
HD	2000	1280 x 720	HD (short side \leq 720 px)
FHD	4000	1920 x 1080	FHD (short side \leq 1080 px)
2K	6000	2560 x 1440	2K (short side \leq 1440 px)
4K	8000	3840 x 2160	4K (short side \leq 2160 px)

VOD's Top Speed Codec (TSC) solution integrates image quality remaster and enhancement, adaptive parameter selection, and V265 encoder, among other video processing features. It can transcode videos to higher quality at

lower bitrates, helping you save network resource costs while delivering a better viewing experience. For TSC transcoding, we recommend the following resolution and bitrate combinations:

Definition	Recommended Bitrate	Recommended Resolution	Resolution Range
SD	350 or leave it empty	640 x 480	SD (short side \leq 480 px)
HD	1350 or leave it empty	1280 x 720	HD (short side \leq 720 px)
FHD	2700 or leave it empty	1920 x 1080	FHD (short side \leq 1080 px)
2K	3500 or leave it empty	2560 x 1440	2K (short side \leq 1440 px)
4K	7500 or leave it empty	3840 x 2160	4K (short side ≤ 2160 px)

Note:

If bitrate is left empty, VOD will set the minimum bitrate automatically based on intelligent analysis of the source video.

Initiating Transcoding Through the Console

Step 1. Activate VOD

Activate VOD. For detailed directions, see Getting Started - Step 1. Activate VOD.

Step 2. Upload a video

Upload a test video. For detailed directions, see Getting Started - Step 2. You can download the video used in this document here. The file ID generated is 3270835008936537687.

Video Managen	nent 💸 test	▼ Su			
Uploaded	Jploading				
Upload Video	Batch Delete Proce	ss Video Quick	Edit More 💌		
Separate key words	with a vertical line " " and separat	e filter conditions by pre	ssing Enter	a,	
Video Name/I	D	Video Status	Video Category 🕈	Uploading Time 🗘	Expiratio
00:00:30	6.mp4 ID:5285890808884169879	⊘ Normal	Other	2020-10-20 17:24:44	Permanen
00:00:30	6.mp4 ID:5285890808844023964	🕑 Normal	Other	2020-10-19 14:50:40	Permanen

Note:

To avoid the transcoding taking too much time, we recommend you use a short video (dozens of seconds) for test .

Step 3. Initiate transcoding

1. On the Video/Audio Management page of the VOD console, select the video you uploaded, and click Transcoding.

VOD	Video Management	Primary application
Service Overview	Uploaded Uploa	ading
▶ Media Assets ^		Upload Video Batch Delete Process Video
 Video Management 		Separate key words with a vertical line " " and separate filter of
 Image Management 		- Video Name/ID
Cold Storage		test.mp4 ID:8602268010602075659 Quick View

2. Select **Transcoding** as the processing type and select a **transcoding template**.

Process Video			×
Using video pr <u>Billing</u> ,	rocessing will incur fees. For deta	ils, see <u>Video Processing</u>	9
Processing Type	 Transcoding Adaptiv Video Audit Task Flo 	e Bitrate Streaming w	
Transcoding Template	Transcoding Template	Common Template	
Watermark Template	No waterma 🔻		
Thumbnail	✓ Thumbnail		
	Confirm Car	icel	
firm. As an example	, the preset templates STD-	-H264-MP4-360P	(ID 100010) and

MP4-540P (ID 100020) are selected in this document. For directions on how to use a custom transcoding template, see Template Configuration.



4. Click Confirm.



Process Video		×
Using video p <u>Billing</u> .	rocessing will incur fees. For details, see <u>Video Processin</u>	g
Processing Type	 Transcoding Adaptive Bitrate Streaming Video Audit Task Flow 	
Transcoding Template	Transcoding Template2 Common Template	e
Watermark Template	No waterma 🔻	
Thumbnail	✓ Thumbnail	
	Confirm	

5. Go to **Task Center**. If the status of the task is "Completed", the video has been successfully transcoded.

Step 4. Get the transcoding output

1. In the VOD console, select the target application. On the **Media Assets > Video/Audio Management** page, if the status of your test video is "Normal", transcoding is finished. Click **Manage** on the right to enter the details page.

VOD	Video Management	Primary application			
Service Overview	Uploaded Upload	ing			
Media Assets ^		Upload Video Batch Delete Process Video	Quick Edit More 🔻		
 Video Management 		Separate key words with a vertical line " " and separate filter conc	litions by pressing Enter	Q	
• Image		- Video Name/ID	Video Status	Video Category ▼	Uploading Time 💲
Cold Storage		test.mp4 ID:8602268010602075659 Quick View	⊘ Normal	Other	2021-10-17 15:42:56
The Later Management					

2. Under the **Transcoding outputs** tab, you will find the transcoding outputs generated by the TD-H264-MP4-360P and STD-H264-MP4-540P templates. You can click **Preview** on the right to play the video or copy the playback URL and share it to others.

▶ Media Assets ^				
 Video Management 	Standard Transcoding List			
• Image Management	Delete			
Cold Storage	Specification	Format	Resolution	Bitrate
Task Management	STD-H264-MP4-360P	MP4	360 x 480	139.14Kbps
System Settings	STD-H264-MP4-540P	MP4	540 x 720	209.81Kbps

Calling TencentCloud APIs to initiate transcoding

Step 1. Prepare a CVM instance

TencentCloud API script needs to be executed on a CVM instance that meets the following requirements:

Region: No limit.

Model: The minimum specification (1 CPU core and 1 GB memory) or higher.

Public network: A public IP address is required, and the bandwidth should be at least 1 Mbps.

Operating system: Official public image Ubuntu Server 16.04.1 LTS 64-bit or Ubuntu Server 18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, see Operation Guide - Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System.

Note:

If you do not have a CVM instance that meets the above conditions, you can also run the script on other Linux (such as CentOS or Debian) or macOS servers with public network access, but you need to modify certain commands in the deployment script based on the operating system.

Step 2. Obtain the TencentCloud API key

An API key (SecretId and SecretKey) is required for calling TencentCloud APIs. If you have not created an API key yet, create one as instructed in Creating an API key for a root account. If you have already created a key, follow the steps in Viewing an API key of a root account to view the key.

Step 3. Activate VOD

Activate VOD. For detailed directions, see Getting Started - Step 1. Activate VOD.

Step 4. Upload a video

Upload a test video. For detailed directions, see Getting Started - Step 2. You can download the video used in this document here.

VOD	Video Management	Primary application
Service Overview	Uploaded Upload	ling
Media Assets ^		Upload Video Batch Delete Process Video
 Video Management 		Separate key words with a vertical line " " and separate filter co
 Image Management 	-	Video Name/ID
Cold Storage		Line 111.mp4 ID:5285890804162014755 Ouick View
Task Management	-	

Note:

To avoid the transcoding taking too much time, we recommend you use a short video (dozens of seconds) for test .

Step 5. Initiate transcoding

1. Log in to the CVM instance prepared in Step 1 and run the following command on the remote terminal:

ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

You need to assign values to SECRET_ID and SECRET_KEY according to the key obtained in Step 2.

2. The above command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote terminal will print the following information:

```
[2020-06-15 20:39:56] Start installing pip3.
[2020-06-15 20:40:06] pip3 is successfully installed.
[2020-06-15 20:40:06] Start installing TencentCloud API Python SDK.
[2020-06-15 20:40:07] TencentCloud API Python SDK is installed.
[2020-06-15 20:40:07] Start configuring API parameters.
[2020-06-15 20:40:07] API parameters are configured.
```

3. Execute the process_media.py script to initiate transcoding.

```
ubuntu@VM-69-2-ubuntu:~$ cd ~/vod-server-demo/transcode_api/; python3 process_media
```

Note:

You need to replace 243791581340253754 in the command with the file ID generated in Step 4.

4. This command will initiate a ProcessMedia request for the video 243791581340253754, transcode the video according to the preset templates 100010 and 100020, and print the response:

{"TaskId": "1400329073-procedurev2-f6bf6f01612369b6db30f2224792a2aft0", "RequestId"

Step 6. Get the transcoding output

1. Go to Task Center. If the status of the task is "Completed", the video has been successfully transcoded.

VOD	Video Management	Primary applicatio	n v	
Service Overview	Uploaded Uploadi	ng		
Media Assets ^		Upload Video	Batch Delete	Process Video
 Video Management 		Separate key words v	vith a vertical line	" " and separate filter co
Image Management		Video Name/ID)	
Cold Storage			test111.mp4 ID:52858908041 Quick View	62014755
🔄 Task Management				

2. When the status of the test video changes to "Normal", the transcoding is finished. Click **Manage** on the right to enter the details page.

VOD	Video Management	Primary application 💌 S			
Service Overview	Uploaded Uploadi	ing			
■ Media Assets ^		Upload Video Batch Delete Process Video	Quick Edit More 🔻		
 Video Management 		Separate key words with a vertical line " " and separate filter conditi	ions by pressing Enter	Q	
• Image		- Video Name/ID	Video Status	Video Category T	Uploading Time 🗘
Cold Storage		test.mp4 ID:8602268010602075659 Quick View	⊘ Normal	Other	2021-10-17 15:42:56

3. Under the **Transcoding outputs** tab, you will find the transcoding outputs generated. You can click **Preview** on the right to play the video or copy the playback URL and share it to others.

· Video Management Standard Transcoding List · Image Management Delete · Cold Storage Specification · Task Management Specification · Task Management STD-H264-MP4-360P · Video Audit StD-H264-MP4-540P · StD-H264-MP4-540P MP4 · Stdo x 720 209.81Kbps	▶ Media Assets ^				
Image Management Delete Cold Storage Specification Format Resolution Bitrate Task Management STD-H264-MP4-360P MP4 360 x 480 139.14Kbps Video Audit StD-H264-MP4-540P MP4 540 x 720 209.81Kbps	 Video Management 	Standard Transcoding List			
Cold Storage Specification Format Resolution Bitrate I Task Management STD-H264-MP4-360P MP4 360 x 480 139,14Kbps Video Audit System Settings STD-H264-MP4-540P MP4 540 x 720 209,81Kbps	• Image Management	Delete			
Task Management STD-H264-MP4-360P MP4 360 x 480 139,14Kbps Video Audit System Settings StD-H264-MP4-540P MP4 540 x 720 209,81Kbps	Cold Storage	Specification	Format	Resolution	Bitrate
System Settings STD-H264-MP4-540P MP4 540 x 720 209.81Kbps	Task Management	STD-H264-MP4-360P	MP4	360 x 480	139.14Kbps
	System Settings	STD-H264-MP4-540P	MP4	540 x 720	209.81Kbps

Auto Transcoding After Uploading (Task Flow)

VOD supports multiple upload methods, including upload through the console, upload from the server, upload from a client and upload by pulling from URLs. Whatever method you use, you can specify a task flow to automatically transcode the video after it is uploaded.

Auto Transcoding After Uploading (Event Notification)

VOD will send notification requests for both uploading and transcoding events. You can initiate transcoding tasks for newly uploaded videos based on the event notifications as well as get the transcoding results from notifications (or from the console as described above). For details about how to use event notifications, see How to Receive Event Notification.

How to Moderate Media Content

Last updated : 2023-04-27 15:00:32

Non-compliant content may expose your business to legal risks and hurt your brand. VOD offers audio/video moderation and image moderation capabilities to help you ensure the compliance of your content.

Audio/Video Moderation

The audio/video moderation feature of VOD analyzes your video and audio content and gives suggestions on whether to publish or block the content.

You can initiate audio/video content moderation in the following two ways:

- 1. Initiate it in the VOD console.
- 2. Call a server-side API.

Using a server-side API to initiate audio/video moderation

The figure below shows how a video application moderates the videos uploaded by users using the server-side API.



1. The video application backend authenticates the content provider and distributes a signature for upload from client.

2. The content provider uploads the content to VOD.

3. VOD sends information including the file ID and playback URL of the uploaded video to the application backend.



4. VOD executes a moderation task (ReviewAudioVideoTask) according to the procedure parameter passed in when the video is uploaded.

5. VOD sends the result to the application backend via the ReviewAudioVideoComplete notification.

If the moderation result is "block", there's a high chance that the content is non-compliant. We recommend you block the content.

If the moderation result is "pass", the probability of the content being non-compliant is low. We recommend you allow the content to pass.

If the moderation result is "review", the probability of the content being non-compliant is high; in this case, manual verification is recommended.

6. The application backend publishes videos whose suggestion is "pass" as well as those that are given a "review" suggestion and have passed manual verification.

7. Viewers request a playback URL for a published video from the application backend.

8. Viewers play the video via the URL (VOD offers acceleration services).

Steps 4-6 ensure that the video obtained in step 7 is compliant.

Note:

In the above process, videos are moderated before being published (only videos that pass the moderation or review are published). You can also use the post-moderation mode, in which videos are published first before moderation is performed (non-compliant content detected will be removed).

Image Moderation

The image moderation feature of VOD analyzes images and gives suggestions on whether to pass or block them. Unlike audio/video moderation, image moderation is performed synchronously, and results are generated immediately.

If the moderation result is "block", there's a high chance that the content is non-compliant. We recommend you block the content.

If the moderation result is "pass", the probability of the content being non-compliant is low. We recommend you allow the content to pass.

If the moderation result is "review", the probability of the content being non-compliant is high; in this case, manual verification is recommended.

You can initiate image moderation in two ways:

1. Initiate it in the VOD console.

2. Call the server-side API ReviewImage.

Billing



For details about how content moderation is billed, see Purchase Guide.

How to Add Complex Watermarks to Videos

Last updated : 2021-03-25 17:52:05

VOD's watermarking feature allows the adding of simple image or text watermarks, but cannot meet more sophisticated needs such as adding text-image watermarks or applying filters to watermarks. Given this, VOD has supported Scalable Vector Graphics (SVG) watermarks, allowing you to design text and image layout as you like, draw your own images, and apply filters, gradients, and other special effects.

What is SVG

SVG is an XML-based markup language for describing two-dimensional vector graphics. It has been widely applied to web standards including CSS, DOM, and JavaScript.

VOD does not set height or width limits for SVG. It can identify the smallest rectangle that contains all the elements of an image and use it as the original dimension of an SVG watermark. In the figure below, the dotted frame is the smallest rectangle identified.



Note:

You can find on the internet different free, web-based SVG editors. Use them to draw the graphics you want and export them as XML files.

Before getting the final XML code, you can manually fine-tune your image, for example, align element attributes or change font size, and check the result in an editor.

How to Add SVG Watermarks

Step 1. Edit an SVG watermark.

1. Use an SVG editor (e.g., the simple tool Tryit Editor, or Online SVG Editor, which incorporates more advanced features) to draw your graphics. The graphics are displayed in real time as you edit. After editing, you can save the code as an HTML file, which you can open with a browser later to check the effect.

Note:

If you need to align different elements, we recommend that you make flexible use of the elements' alignable attributes and check if the alignment is effective by changing the values of the elements, for example, placing images next to text, or reducing/increasing text length. For detailed instructions, see this SVG tutorial. An example is offered below.

Step 2. Create an SVG watermark template.

Call the CreateWatermarkTemplate API and specify parameters including the watermark coordinates and dimensions. After the creation, you get a watermark template ID.

Step 3. Add the SVG watermark to a video.

For how to start a video processing task and get the result, see Video Processing Task System.

Take the ProcessMediaAPI as an example. In Example2 Initiating a transcoding task, you should setWatermarkSet.N.Definitionto the template ID obtained in step 2 and, as an SVG watermark is used, passthe XML code obtained in step 1 inWatermarkSet.N.SvgContent

Example

This section uses an example to guide you through the process of adding a complex watermark that contains an image and replaceable text.

Use case

A client wants to watermark videos and has the following requirements:

The watermark consists of a brand logo and ID of the logged in account (text).

The watermark appears in the top right corner of videos. The distance between its origin and the right and top border of videos is 2% of video width and 5% of video height respectively.

The width of the watermark is 30% of video width, and the height scales proportionally.

The text is beneath the logo and aligns to right of the logo.

The font for the text is SimHei, the background in white, with Gaussian blur and shadow in black. The font size is 50 px when the brand logo is not scaled.

Step 1. Edit the SVG watermark.



Below is the XML source code for the SVG watermark:

Result checking:

Method 1: copy the above code to the input field of Tryit Editor, and click **Run** at the top. The watermark appears on the right side:





Method 2: save the code as an HTML file and open it with a browser. The watermark (white background) in figure 2 below appears.



Code explanation

Parameter	Description	Attribute
<svg></svg>	Define the SVG canvas	width="1000px" height="1000px" : both height and are 1000 px. Just make sure that the canvas is large enough to include all the elements of the watermark.
<filter id="filter"></filter>	Define the filter to be used	-
<fegaussianblur></fegaussianblur>	Set the Gaussian blur filter	stdDeviation="2"
<feoffset></feoffset>	Set the filter offset	dx="0" dy="3" : offset the filter by 3 px down.
<image id="img_watermark"/>	Brand logo	<pre>xlink:href="data:image/png;base64, {Base64-encoded image data}" :reference a local image. height="185px" width="256px" :set the original aspect ratio.</pre>



		x="74.4%" $y="0px"$: as the logo is above the text, set the Y-axis offset to 0 px. Keep <i>adjusting</i> the X-axis offset until the expected result is achieved ($x="74.4$ %").
<text id="text_watermark_shadow"></text 	Add a shadow to text	<pre>font-family="SimHei" font- style="Regular" font-size="50px" : Set font and font size. text-anchor="end" : set the end of the text as its original position for alignment. x="100%" : set text-anchor and x to pin the last character of the text to the right of the canvas so as to adjust the position of the brand logo (x attribute of <image id="img_watermark"/>). style="opacity:1;" : set the opacity. fill="black" : set the shadow-fill-color to black. filter="url(#filter) : apply the filter whose id is filter. y="245px" : set the Y-axis offset. The height of the brand logo is 185 px, and the font size 50 px, which is basically equivalent to the font height, so y must not be smaller than 185+50=235 . After testing the value is set to 245.</pre>
<text id="text_watermark"></text>	Text	Most of this parameter's attributes are the same as those of <text id="text_watermark_shadow"> , but it does not use a filter (without the filter attribute), and the text-fill-color is white (fill="white").</text

When checking the final result, you are advised to change the length of the text, for example, by replacing

@Tencent with @Tencent is a kind person to see if the result still meets the requirements.

To use a different user ID, just replace the value of <text> in the SVG code.

Step 2. Create an SVG watermark template.

```
https://vod.tencentcloudapi.com/?Action=CreateWatermarkTemplate
&Type=svg
&Name=Test
&CoordinateOrigin=TopRight
&XPos=2%
&YPos=5%
```

&SvgTemplate.Width=30S% &SvgTemplate.Height=0px

```
&<Common request parameters>
```

Parameter description:

Parameter	Description
Type=svg	Set the watermark type to SVG.
Name=Test	Set the name of the template (optional).
CoordinateOrigin=TopRight	Pin the watermark to the top right of the video.
XPos=2%	Set the distance between the watermark origin and the right border of videos to 2% of video width.
YPos=5%	Set the distance between the watermark origin and the top border of videos to 5% of video height.
SvgTemplate.Width=30S%	Set the watermark width to 30% of video width.
SvgTemplate.Height=0px	The height of the watermark scales proportionally.

Suppose the ID of the SVG watermark template created is 12345.

Step 3. Add the SVG watermark to a video.

Initiates a video processing task:

```
https://vod.tencentcloudapi.com/?Action=ProcessMedia
&FileId=5285485487985271487
&MediaProcessTask.TranscodeTaskSet.0.Definition=30
&MediaProcessTask.TranscodeTaskSet.0.WatermarkSet.0.Definition=12345
&MediaProcessTask.TranscodeTaskSet.0.WatermarkSet.0.SvgContent={the XML code in ste
&<Common request parameters>
```

Below is an example of the result



Appendix

Supported fonts

SimHei:style=Regular Roboto:style=Bold Contact us if you want other fonts supported.

Distribution and Playback How to Use Key Hotlink Protection

Last updated : 2022-12-16 14:16:08

Overview

Demo features

This demo describes how to use the key hotlink protection mechanism of VOD, including enabling key hotlink protection in the console, building a hotlink protection signature distribution service, and playing back a video with a hotlink protection signature.

Architecture and process

An HTTP service is built based on SCF in the demo to receive the requests for getting hotlink protection signatures from clients. It gets the original URL of a video in VOD from the request body, calculates a signature, and returns the URL with the signature to the client.

The system mainly involves four components: developer (you), API Gateway, SCF, and VOD. Here, API Gateway and SCF are the deployment objects of this demo as shown below:



SCF

The specific business process is as follows:

1. Get the original URL of the video in the VOD console (in the actual production environment, it should be the player that requests the video URL from the business backend; to simplify the process, this document takes your operation as an example to simulate such business behavior here).

2. Use the original URL of the video to request a hotlink protection signature from SCF.

3. Use the video URL with the hotlink protection signature to request VOD CDN to play back the video.

Note:

The SCF code in the demo is developed based on Python 3.6. SCF also supports other programming languages such as Python 2.7, Node.js, Go, PHP, and Java for your choice as needed. For more information, please see Development Guide.

Fees

The VOD key hotlink protection signature distribution service demo provided in this document is open-source and free of charge, but it may incur the following fees during service building and use:

Fees for purchasing a Tencent Cloud CVM instance to run the service deployment script. For more information, please see Instance Billing Modes.

Fees for using signature distribution service provided by SCF. For more information, please see Billing Mode and Free Tier.

Fees for using Tencent Cloud API Gateway to provide public network APIs for SCF. For more information, please see Billing Overview.

Fees for VOD storage of uploaded videos.

VOD storage space will be taken up by uploaded videos. For more information, please see Video Storage Pricing.

Quickly Deploying Key Hotlink Protection Signature Distribution Service

Step 1. Prepare a CVM instance

The deployment script needs to be executed on a CVM instance meeting the following requirements: Region: not limited.

Model: the minimum official configuration (1 CPU core and 1 GB memory) is sufficient.

Public network: a public IP is required, and the bandwidth should be at least 1 Mbps.

Operating system: official public image Ubuntu Server 16.04.1 LTS 64-bit or Ubuntu Server

18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, please see Operation Guide -Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System, respectively.

The key hotlink protection signature distribution service demo itself does not depend on CVM but only uses CVM to run the deployment script.

If you do not have a CVM instance satisfying the above conditions, you can also run the script on another Linux (such as CentOS or Debian) or macOS server with public network access, but you need to modify certain commands in the deployment script based on the operating system. Please search for the specific modification method by yourself.

Step 2. Activate VOD and configure key hotlink protection

1. Activate the VOD service as instructed in Getting Started - Step 1.

2. After activation, enable key hotlink protection as instructed in Setting Hotlink Protection and record the hotlink protection key:

Key Hotlink Protection	Enable Key Hotlink Protection			
Key hotlink protection URL carries video playback contr	Hotlink Protection Key	Genera		
Key Hotlink Protection O NO key hotlink protection rule set.		Confirm		

Note:

Here, enable key hotlink protection instead of referer hotlink protection. If you enable referer hotlink protection at the same time, the request may fail as the test method below does not meet the corresponding requirements.

Step 3. Get the API key and APPID

Your API key (i.e., SecretId and SecretKey) and APPID are required for deploying and running the key hotlink protection signature distribution service demo.

If you have not created an API key yet, please generate one as instructed in Root Account Access Key. If you have already created a key, please get it as instructed in the same document.

You can view the APPID on the Account Information page in the console as shown below:

Account Center	Account Information			
Account Information		Basic Informatio	on	
Security Setting		Account Email	⊉qq.com	
Project Management		Account Alias	@qq.com 🧨	
Identity Verification		Account ID	1000	
Message Subscription 🖪		APPID	1301	

Step 4. Deploy the hotlink protection signature distribution service

Log in to the CVM instance prepared in step 1 as instructed in Logging into Linux Instance in Standard Login Method and enter and run the following command on the remote terminal:



ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

Please assign the corresponding values obtained in step 3 to SECRET_ID, SECRET_KEY, and APPID in the command and assign the hotlink protection key obtained in step 2 to ANTI_LEECH_KEY.

This command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote terminal will print the following information:

```
[2020-06-04 15:57:10] Start checking npm.
[2020-06-04 15:57:18] npm is successfully installed.
[2020-06-04 15:57:18] Start installing ServerLess.
[2020-06-04 15:57:19] ServerLess is successfully installed.
[2020-06-04 15:57:20] Start deploying the VOD key hotlink protection signature dist
[2020-06-04 15:57:30] The deployment of the VOD key hotlink protection signature di
[2020-06-04 15:57:32] Service address: https://service-xxxxxxx-125xxxxxx.gz.apigw
```

Copy the address of the signature distribution service in the output log (which is https://service-xxxxxxx-125xxxxxx.gz.apigw.tencentcs.com/release/anti_leech_sign in this example).

Note:

If the following warning is displayed in the output log, it is generally because the CVM instance cannot immediately parse the service domain name deployed just now. You can ignore this warning.

[2020-04-25 17:18:44] Warning: the key hotlink protection signature distribution se

Step 5. Test key hotlink protection

Upload a test video to VOD as instructed in Uploading Video - Local Upload. After the video is uploaded, click **Quick** View and click **Copy URL** on the right to copy the video URL.



Video Management	Primary application 🔹				test111.mp4	
Uploaded Upload	ling				ID	8(
	Upload Video Batch Delete	Process Video Quick Edit Mo	ore 🔻		Video Name	test111.mp4 🎤
	Separate key words with a vertical line " " and	separate filter conditions by pressing Enter	Q,		Category	Other 🧨
	Video Name/ID	Video Status	Video Category T	Upload	label	-
	ID: Quick View	⊘ Normal	Other	2021-10	Size	589.43KB
	111_2021-08-12-10-04 ID:37019259222734781 Ouirck View	-58_2021-08-12-10-08-46 62	Other	2021-08	Duration	00:00:04 Permanent 🎤
	Contraction	-22_2021-08-12-10-08-46 33 ② Normal	Other	2021-08	File Description	1
	111_2021-08-12-10-03 ID:37019259222734781	-22_2021-08-12-10-08-22 09 Ø Normal	Other	2021-08	Copy All URLs Specification	Batch Delete
	Quick View	-58 2021-08-12-10-04-58			✓ Original Video	MP

On the command line on the CVM instance, run the curl command to try directly accessing this URL. The access will be rejected by the server for non-compliance with the key hotlink protection rule, and the HTTP return code will be 403 (during the test, please replace the URL in the command with the actual URL, which also applies below):

```
ubuntu@VM-69-2-ubuntu:~$ curl -I "http://125xxxxxx.vod2.myqcloud.com/f888c998vodcq
HTTP/1.1 403 Forbidden
Server: NWS_VP
Connection: keep-alive
Date: Thu, 04 Jun 2020 08:27:54 GMT
Content-Type: text/plain
Content-Length: 14
```

On the command line on the CVM instance, run the curl command to request the URL with the hotlink protection signature from the service deployed in step 4 (-d means to initiate the request in POST method, and the carried parameter is the video URL):

```
ubuntu@VM-69-2-ubuntu:~$ curl -d 'http://125xxxxxx.vod2.myqcloud.com/f888c998vodcq
http://125xxxxxx.vod2.myqcloud.com/f888c998vodcq125xxxxxx/c849148f528xxxxxxxxx
```

Run the curl command again to access the URL with the hotlink protection signature obtained in the previous step, and the URL can be accessed normally (the HTTP return code will be 200):

```
ubuntu@VM-69-2-ubuntu:~$ curl -I "http://125xxxxxx.vod2.myqcloud.com/f888c998vodcq
HTTP/1.1 200 OK
Server: tencent-cos
Connection: keep-alive
Date: Thu, 04 Jun 2020 08:37:17 GMT
```


```
Last-Modified: Fri, 22 May 2020 15:06:15 GMT
Content-Type: video/mp4
Content-Length: 232952632
Accept-Ranges: bytes
ETag: "1da6be3a0d1da5edae4ff0b1feff02cf-223"
x-cos-hash-crc64ecma: 16209801220610226954
x-cos-request-id: NWVkOGIyYmVf2DUyMzYyNjRfYWMwMF85YjkyNzA=
X-Daa-Tunnel: hop_count=4
X-NWS-LOG-UUID: b404f43e-3c86-4c54-8a78-fb78e4e85cf2 add71e19fb08c6d9dbe1b21a2fb157
Access-Control-Allow-Credentials: true
Access-Control-Allow-Credentials: true
Access-Control-Allow-Headers: Origin,No-Cache,X-Requested-With,If-Modified-Since,Pr
Access-Control-Allow-Methods: GET,POST,OPTIONS
Access-Control-Allow-Origin: *
```

Note:

You can access the URL with the hotlink protection signature in a browser and verify the signature by playing back the video. However, this method has certain requirements for the video format. Generally, H.264-encoded .mp4 videos have high compatibility, which are recommended. You can also use a third-party tool such as Postman to send HTTP requests for test. Please search for the specific usage by yourself.

System Design Description

API protocol

The key hotlink protection signature distribution function uses API Gateway to provide APIs. The specific API protocol is as detailed below:

Service	Function Name	API Form	Request Content	Response Content
Key hotlink protection signature distribution	anti_leech_sign	HTTP POST	Original video URL	URL with hotlink protection signature

Signature distribution service code interpretation

1. main_handler() is the entry function.

2. Call parse_conf_file() and read the configuration information from the config.json file. The

configuration items are as described below (for specific parameters, please see Key Hotlink Protection):

Field	Data Type	Description
key	String	Key hotlink protection key
t	Integer	Signature validity period in seconds. When a request is being processed, this parameter plus the current time on the SCF server will be `t` in the



		hotlink protection parameters
exper	Integer	Preview duration
rlimit	Integer	Maximum number of client IPs that can access the signature

3. Parse the Dir parameter from the request body, generate the t and us parameters locally, and read the exper and rlimit parameters from the configuration file:

```
original_url = event["body"]
parse_result = urlparse(original_url)
directory = path.split(parse_result.path)[0] + '/'
# Signature parameters
timestamp = int(time.time())
rand = random.randint(0, 999999)
sign_para = {
    "t": hex(timestamp + configuration['t'])[2:],
    "exper": configuration['exper'],
    "rlimit": configuration['rlimit'],
    "us": rand
}
```

4. Call generate_sign() to calculate the hotlink protection signature. For the specific algorithm, please see Key Hotlink Protection.

5. Generate the QueryString and add it at the end of the original URL to concatenate a URL with the hotlink protection signature:

```
sign_para["sign"] = signature
query_string = urlencode(sign_para)
new_parse_result = parse_result._replace(query=query_string)
signed_url = urlunparse(new_parse_result)
```

6. Return the signature. For the formats and descriptions of the returned data, please see Overview of API Gateway Trigger.

How to Prevent Malicious Video Hosting

Last updated : 2022-03-24 15:32:21

User-generated content (UGC) and professionally generated Content (PGC) platforms are two common scenarios in the video industry where video content can be freely uploaded and shared.

However, third-party video platforms may impersonate normal users to upload videos to your platform and then put the URLs of those videos on their own platforms. In this way, they can "live" on your platform like a parasite and get "free" access to video storage and playback acceleration. As a result, your video platform is used maliciously by others as a free video hosting service, which is called "malicious video hosting".

Malicious video hosting can cause serious economic losses since all the storage, bandwidth, and traffic fees incurred by the parasites have to be borne by you.

Causes of Malicious Video Hosting

How UGC/PGC platforms interact with others normally





Note:

Arrows in the figure represent the network request directions.

Generally, a UGC or PGC video platform interacts with content providers, content consumers, and VOD in the

following ways (for more information on steps 1–3, please see Upload from Client):

1. The application backend authenticates the content provider and distribute to them a video upload signature after authentication is passed.

2. The content provider uploads the content to be shared to VOD.

3. VOD notifies the application backend of relevant information such as the fileId and playback URL of the uploaded video.

4. The content consumer requests the playback URL from the application backend.

5. The content consumer accelerates video playback via VOD through the URL.

How malicious video hosting is implemented



Note:

Arrows in the figure represent the network request directions.

A malicious third-party video platform impersonates a normal user of your platform:

It upload its own videos to VOD as a video provider (steps 1 and 2).

Then, it gets the playback URLs of these videos from your platform as a consumer (step 4).

The users of the malicious platform get these URLs (step 4) and accelerate playback through VOD (step 5).

Core causes of problem

The ultimate purpose of malicious video hosting is to steal others' CDN bandwidth resources (while taking advantage of their storage resources). Malicious users do so mainly for the following:

Step 4. The malicious platform can quickly get the playback URLs from the application, store them, and distribute them to its own users.

Step 5. After the users of the malicious platform get the URLs, they can accelerate video playback unlimitedly.

Malicious Video Hosting Prevention

In view of the core causes of malicious video hosting listed above, the key solutions lie in:

Preventing **unrestricted access to playback URLs** as mentioned in step 4. Preventing **unrestricted playback acceleration** as mentioned in step 5. The following describes how VOD helps you restrict **playback** of and **access** to URLs.

Restricting playback of URLs

VOD's key hotlink protection provides the ability to limit the number of devices allowed to play back a video from a URL, so as to prevent the URL from being distributed to any number of devices for playback. In order to implement effective control of the playback URL, you need to enable hotlink protection in the console; in step 4, a hotlink protection-enabled URL needs to be generated on the application backend according to the key hotlink protection URL generation rules (please see the example of "maximum number of IPs allowed for playback at a video playback address") in order to limit the validity period of the URL and the number of IPs allowed for playback.

Restricting access to URLs

Restricting playback of URLs alone cannot effectively prevention malicious video hosting. This is because in step 4, a malicious platform can make countless requests for different hotlink protection-enabled URLs for the same video and then distribute those URLs to its own users, thus bypassing the restriction on the number of IPs allowed for playback. In response, the application backend needs to verify user identity in step 4 and impose frequency control, i.e., how many times an individual user can get the same playback URL within a specified period of time. This can prevent malicious users from getting a large number of video playback addresses in a short period of time.

How to Receive Event Notification

Last updated : 2023-05-15 17:39:11

Overview

About this document

In this document, we will run you through the process of uploading and transcoding a video and show you how to use VOD's event notifications.

Architecture and workflow

In the demo, an HTTP server was built based on SCF to receive event notification requests from VOD. The server initiates transcoding tasks and gets the transcoding results based on the NewFileUpload and ProcedureStateChanged notifications it receives.

The system consists of four main components: the console, API Gateway, SCF, and VOD. API Gateway and SCF are the deployment objects of the demo.



The workflow is as follows:

1. Upload a video to the VOD console.

2. VOD sends a NewFileUpload notification request to the demo.

3. The demo parses the notification and calls VOD's ProcessMedia API to transcode the uploaded video using the preset transcoding templates 100010 and 100020.

4. After completing the transcoding task, VOD sends a ProcedureStateChanged notification request to the demo.

5. The demo parses the notification and prints the URL of the transcoding output in SCF logs.

Note:

The SCF code in the demo is developed based on Python 3.6. SCF also supports other programming languages such as Python 2.7, Node.js, Go, PHP, and Java. For more information, see Code Development.

Fees

The demo for receiving VOD event notifications provided in this document is open-source and free of charge, but to build the demo, you may incur the following fees:

Fees for purchasing a Tencent Cloud CVM instance to execute the script. For more information, see CVM Billing Mode.

Fees for using SCF to distribute signatures. For more information, see Pay-As-You-Go and Free Tier.

Fees for using Tencent Cloud API Gateway to provide public network APIs for SCF. For more information, see Shared Instance Billing.

Fees for storing videos uploaded to VOD. For details, see Pay-As-You-Go and Prepaid Packages. Fees for transcoding videos stored in VOD. For details, see Pay-As-You-Go and Prepaid Packages.

Impact on your production environment

The demo uses VOD's event notification mechanism, for which you need to configure an event notification address. If there is already a VOD-based production environment under your account, changing the event notification address may affect your active business. Therefore, **before doing so, make sure it will not affect your production environment. If you are not sure, please use a new account to deploy the demo.**

Quickly Deploying Event Notification Receipt Service

Step 1. Prepare a CVM instance

The deployment script needs to be executed on a CVM instance that mees the following requirements: Region: No limit.

Model: The minimum specification (1 CPU core and 1 GB memory) or higher.

Public network: A public IP address is required, and the bandwidth should be at least 1 Mbps.

Operating system: Official public image Ubuntu Server 16.04.1 LTS 64-bit or Ubuntu Server 18.04.1 LTS 64-bit .

For detailed directions on how to purchase a CVM instance and reinstall the system, see Operation Guide - Creating Instances via CVM Purchase Page and Operation Guide - Reinstalling System.

Note:

The demo itself does not depend on CVM, but it needs a CVM instance to run the deployment script.

If you do not have a CVM instance that meets the above conditions, you can also run the script on other Linux (such as CentOS or Debian) or macOS servers with public network access, but you need to modify certain commands in the deployment script based on the operating system.

Step 2. Activate VOD

Activate VOD. For detailed directions, see Getting Started - Step 1. Activate VOD.

Step 3. Get the API key and APPID

Your API key (i.e., SecretId and SecretKey) and APPID are required for deploying and running the demo. If you have not created an API key yet, create one as instructed in Creating an API key for a root account. If you have already created a key, follow the steps in Viewing an API key of a root account to view the key. You can view your APPID on the Account Information page of the console.

Account Center	Account Information		
Account Information		Basic Informatio	n
Security Setting		Account Email	<u>മ</u> qq.com
Project Management		Account Alias	@qq.com 🎤
Identity Verification		Account ID	1000
Message Subscription 🛛		APPID	1301

Step 4. Deploy the notification receipt service

Log in to the CVM instance prepared in Step 1 and run the following command on the remote terminal:

ubuntu@VM-69-2-ubuntu:~\$ export SECRET_ID=AKxxxxxxxxxxxxxxxxxxxxxx; export SECRET_

Note:

You need to assign values to SECRET_ID, SECRET_KEY, and APPID according to the key and APPID obtained in Step 3.

This command will download the demo source code from GitHub and automatically run the installation script. The installation process will take several minutes (subject to the CVM network conditions), during which the remote device will print the following information:

```
[2020-06-05 17:16:08]Start checking npm.
[2020-06-05 17:16:12] npm is successfully installed.
[2020-06-05 17:16:12]Start installing serverless.
[2020-06-05 17:16:13]Serverless is successfully installed.
[2020-06-05 17:16:14] Start deploying the event notification receipt service.
[2020-06-05 17:16:24] The event notification receipt service is deployed.
[2020-06-05 17:16:26] Service address: https://service-xxxxxxx-125xxxxxx.gz.apigw
```

Copy the address of the event notification receipt service in the output log (which is https://service-

xxxxxxx-125xxxxxx.gz.apigw.tencentcs.com/release/callback in this example).

Note:

If the following warning is printed in the output log, it is probably because the CVM instance cannot parse the domain deployed immediately. You can ignore this warning.

[2020-04-25 17:18:44] Warning: The event notification receipt service failed the te

Step 5. Configure the event notification address

Note:

As mentioned in Impact on your production environment, before you perform the following operations, please make sure that your active business does not depend on VOD event notifications.

- 1. Log in to the VOD console and select **Application Management** on the left sidebar.
- 2. Select the target application.

3. Click **Callback Settings** on the left sidebar and click **Set**. For **Event Notification Method**, select "Normal Callback", and enter the address obtained in Step 4. Select all event notification types, and click **Confirm**.

allback Settings	😵 test 🔹	St	
 For more information You cannot cancel to 	on about selecting callback types, se ask flow status change callback, vide	e <u>Callback Configuration Guide</u> P eo editing completion callback an	d video clipping complet
Set			
Event Notification Method	O Normal Callback O Reliab	le Callback	
Callback URL	https://test.com	${\boldsymbol{ \oslash}}$	
Event Notification	 Finished video uploading 	✓ Deleted the video	Finished video composition
	✓ Task flow status changed	Finished video editing	
	▲ Legacy Types(i)		
	Finished video transcoding	 Finished screencapturing by time points in the video 	✓ Finished video splic
	 Finished screencapturing of image sprite in the video 		
Confirm Cance	el		

Note:

If you see two callback URL configurations (v2.0 and v3.0) in the console, configure v3.0.

Step 6. Test the demo

1. Upload a test video to VOD (select **No processing after upload**). After the video is uploaded, if the status of the video on the **Uploaded** page is "Processing", it indicates that the demo has received the **NewFileUpload** notification and initiated a transcoding task.

2. After the transcoding is finished (status becomes "Normal"), click **Quick View**, and you will see the two transcoding outputs for the file on the right.

3. Log in to the SCF console and go to the log page. In the latest log, you can see that the URLs of the two output files have been printed. You can use SCF to record the URLs in your database or send them to viewers.

Note:

There may be a delay in log generation. If you can't find the URLs, please wait for a minute or two and click **Reset** to refresh the page.

System Design

API protocol

The event notification receipt function uses API Gateway to provide APIs. For the API protocols, see Video Upload Completion and Task Flow Status Change.

Code interpretation

1. main_handler() is the entry function.

2. Call	<pre>parse_conf_file()</pre>	to read configuration information from the	config.json	file.
---------	------------------------------	--	-------------	-------

Field	Туре	Description
secret_id	String	The API key.
secret_key	String	The API key.
region	String	The TencentCloud API request region, which can be any region.
definitions	Array of Integer	The transcoding template.
subappid	Integer	The VOD subapplication the event notification is from.

3. For NewFileUpload event notifications, call deal_new_file_event() to parse the request and get the file ID of the uploaded video.

```
if event_type == "NewFileUpload":
    fileid = deal_new_file_event(body)
    if fileid is None:
        return ERR_RETURN
```



4. Call trans_media() to initiate transcoding, output the API's response packets to SCF logs, and send the response packets to the event notification service of VOD.

```
rsp = trans_media(configuration, fileid)
if rsp is None:
    return ERR_RETURN
print(rsp)
```

5. In trans_media(), call the TencentCloud API ProcessMedia:

```
cred = credential.Credential(conf["secret_id"], conf["secret_key"])
client = vod_client.VodClient(cred, conf["region"])

method = getattr(models, API_NAME + "Request")
req = method()
req.from_json_string(json.dumps(params))

method = getattr(client, API_NAME)
rsp = method(req)
return rsp
```

6. For ProcedureStateChanged event notifications, call deal_procedure_event() to parse the request, get the URL of the transcoding output, and print it in SCF logs:

```
elif event_type == "ProcedureStateChanged":
    rsp = deal_procedure_event(body)
    if rsp is None:
        return ERR_RETURN
```

How to Migrate Files from Origin Server to VOD

Last updated : 2022-08-03 10:37:15

Overview

VOD Migrate Tool is an all-in-one tool that integrates data migration features. By writing a simple configuration file, you can quickly migrate media files at the source address to VOD.

Supported Data Sources

Local folder URL list Tencent Cloud COS AWS S3 Alibaba Cloud OSS Qiniu Kodo

Operating Environments

System environment

Windows, Linux, and macOS

Software dependency

Python 2.7, 3.4 and above Latest version of pip

Installation

Installing via pip (recommended)

You can install the SDK into your project through pip. If you haven't installed pip in your project environment yet, install it first as instructed at pip's official website.



pip install vodmigrate

Installing by using source package

You can click here to download the source code. Download the latest code and decompress:

```
git clone https://github.com/tencentyun/vod-migrate.git
cd vod-migrate
python setup.py install
```

Example

Run the following command:

vodmigrate config.toml

Note:

After the migration is completed, the result will be output to the directory corresponding to the configuration item migrateResultOutputPath , and the filename will be vod_migrate_result.txt .

Configuration Files

The configuration file is in TOML format (for more information, please see config_template.toml. Make sure that the file is encoded in UTF-8). Configure the following file content:

1. Configure the migration type

type indicates the migration type, which is filled in by users based on their migration needs. For example, to migrate local data to VOD, users need to configure type=migrateLocal for [migrateType] .

```
[migrateType]
type="migrateLocal"
```

Currently, the following migration types are supported:

migrateType	Description
migrateLocal	From local system to VOD
migrateUrl	From download URL to VOD

migrateCos	From Tencent Cloud COS to VOD
migrateAws	From AWS S3 to VOD
migrateAli	From Alibaba Cloud OSS to VOD
migrateQiniu	From Qiniu Kodo to VOD

2. Configure the migration task

You can configure a migration task based on your actual needs, including information for the destination VOD and task-related configurations.

```
# Common configuration for the migration tool
[common]
secretId = "SECRETID"
secretKey = "SECRETKEY"
region = 'REGION'
subAppId = 0
concurrency = 5
supportMediaClassification = [ 'video', 'audio', 'image' ]
excludeMediaType = [ ]
migrateDbStoragePath = ''
migrateResultOutputPath = ''
```

Name	Description
secretId	SecretId of your key. Replace SECRETID with your real key information, which can be obtained on the TencentCloud API key page in the CAM console.
secretKey	SecretKey of your key. Replace SECRETKEY with your real key information, which can be obtained on the TencentCloud API key page in the CAM console.
region	Access point region, i.e., the region where to request a VOD server. This is different from the storage region. For more information, please see Region List.
subAppId	ID of a subapplication in VOD. If you need to migrate a file into a subapplication, enter the subapplication ID in this field; otherwise, leave it empty.
concurrency	Number of concurrently migrated files. Maximum value: 50
supportMediaClassification	List of media types supported for migration. Valid values: video, audio, image
excludeMediaType	List of file types to be excluded
migrateDbStoragePath	Save path of the migrated db . If this parameter is left empty, it means the



	current directory.
migrateResultOutputPath	Save path of the migration result (one migration record corresponds to one line of JSON string). If this parameter is left empty, it means the current directory.

File type description:

Video: MP4, TS, FLV, WMV, ASF, RM, RMVB, MPG, MPEG, 3GP, MOV, WEBM, MKV, and AVI. **HLS and DASH** are not supported.

Audio: MP3, M4A, FLAC, OGG, and WAV

Image: JPG, JPEG, PNG, GIF, BMP, TIFF, AI, CDR, and EPS

3. Configure the data source

Configure each section according to the migration type described in [migrateType] . For example, if the configuration item of [migrateType] is type=migrateLocal , you only need to configure the [migrateLocal] section.

3.1 Configure a local data source migrateLocal

If you migrate a local file to VOD, configure this section. The specific configuration items and descriptions are as follows:

```
# Configuration section for migration from a local system to VOD
[migrateLocal]
localPath = ''
excludes = [ ]
```

Configuration Item	Description	
localPath	Local path, which should be an absolute path	
excludes	Absolute path of the directory to be excluded, which means that some files in the directory at localPath are not to be migrated	

3.2 Configure a URL list data source migrateUrl

If you migrate files from a specified URL list to VOD, configure this section. The specific configuration items and descriptions are as follows:

```
# Configuration section for migration from a URL list to VOD
[migrateUrl]
urllistPath=D:\\\\folder\\\\urllist.txt
```



Configuration Item	Description
urllistPath	Absolute path of the file storing the URL list. The file content is URL text containing one original URL address per line.

Note:

To migrate large local files to VOD, you're advised to use the pullUpload API.

3.3. Configure a COS data source (migrateCos)

If you migrate files from Tencent Cloud COS to VOD, configure this section. The specific configuration items and descriptions are as follows:

```
# Configuration section for migration from Tencent Cloud COS to VOD
[migrateCos]
region = 'ap-shanghai'
bucket = 'examplebucket-1250000000'
secretId = 'COS_SECRETID'
secretKey = 'COS_SECRETKEY'
prefix = ''
```

Configuration Item	Description
region	Region information of the source bucket. For more information, see Regions and Access Endpoints.
bucket	Name of the source bucket in the format of <bucketname-appid>. The bucket name mustincludeAPPID, such asexamplebucket-1250000000.</bucketname-appid>
secretId	SecretId of the key of the account to which the source bucket belongs. You can view this parameter in API Keys.
secretKey	SecretKey of the key of the account to which the source bucket belongs. You can view this parameter in API Keys.
prefix	Prefix of the path to be migrated. If all data in the bucket needs to be migrated, leave the prefix empty.

3.4 Configure an AWS data source migrateAws

If you migrate files from AWS to VOD, configure this section. The specific configuration items and descriptions are as follows:

Configuration section for migration from AWS S3 to VOD



```
[migrateAws]
region = 'ap-northeast-2'
bucket = 'bucket-aws'
accessKeyId = 'AccessKeyId'
accessKeySecret = 'AccessKeySecret'
prefix = ''
```

Configuration Item	Description
region	AWS S3 region
bucket	AWS S3 bucket name
accessKeyld	Replace AccessKeyId with your real key information
accessKeySecret	Replace AccessKeySecret with your real key information
prefix	Prefix of the path to be migrated. If all data in the bucket needs to be migrated, leave the prefix empty

3.5 Configure an Alibaba Cloud OSS data source migrateAli

If you migrate files from Alibaba Cloud OSS to VOD, configure this section. The specific configuration items and descriptions are as follows:

```
# Configuration section for migration from Alibaba Cloud OSS to VOD
[migrateAli]
bucket = 'bucket-aliyun'
accessKeyId = 'yourAccessKeyId'
accessKeySecret = 'yourAccessKeySecret'
endPoint = 'oss-cn-hangzhou.aliyuncs.com'
prefix = ''
```

Configuration Item	Description
bucket	Alibaba Cloud OSS bucket name
accessKeyId	Replace yourAccessKeyId with your real key information
accessKeySecret	Replace yourAccessKeySecret with your real key information
endPoint	Alibaba Cloud endpoint address
prefix	Prefix of the path to be migrated. If all data in the bucket needs to be migrated, leave the prefix empty

3.6 Configure a Qiniu data source migrateQiniu

If you migrate from Qiniu to VOD, configure this section. The specific configuration items and descriptions are as follows:

```
# Configuration section for migration from Qiniu Kodo to VOD
[migrateQiniu]
bucket = 'bucket-qiniu'
accessKeyId = 'AccessKey'
accessKeySecret = 'SecretKey'
endPoint = 'www.bkt.clouddn.com'
prefix = ''
```

Configuration Item	Description
bucket	Qiniu Kodo bucket name
accessKeyId	Replace AccessKey with your real key information
accessKeySecret	Replace SecretKey with your real key information
endPoint	Download URL of Qiniu Kodo, which corresponds to downloadDomain
prefix	Prefix of the path to be migrated. If all data in the bucket needs to be migrated, leave the prefix empty

Restrictions

The tool is designed as a one-time migration tool. The migration has three stages: **origin server file scanning**, **migrating**, and **migration completed**. After the file scan is completed, if the configuration needs to be changed, the db file must be cleared (i.e., deleting <code>migrate.db</code> or modifying the db storage path) to avoid errors with configuration file MD5 verification.

The migrated files must be displayed with the file extension.

HLS/DASH files cannot be migrated currently.

After the migration, the directory relationship between the original videos cannot be maintained, and each video has an independent <code>FileId</code>, all of which are not related to each other.

Migration Process

1. The configuration file is read, the corresponding configuration section is read according to the migration type, and parameters are checked.

2. The origin server is scanned according to the migration type, and migration tasks are generated.

3. After the scan is completed, the migration is performed, and the results of each task and the overall progress are printed.

4. After the migration is completed, the details are output to the result file.

[2020-06-23 11:03:15,077]	build tasks
[2020-06-23 11:03:16,611]	add migrate task: E:\cloud\vod_migrate\media\fancybg.jpg
[2020-06-23 11:03:16,613]	add migrate task: E:\cloud\vod_migrate\media\Wildlife - 副本 (2).mp4
[2020-06-23 11:03:16,616]	add migrate task: E:\cloud\vod_migrate\media\Wildlife - 副本.mp4
[2020-06-23 11:03:16,625]	add migrate task: E:\cloud\vod_migrate\media\Wildlife.mp4
[2020-06-23 11:03:16,626]	add migrate task: E:\cloud\vod_migrate\media\中文.jpg
[2020-06-23 11:03:16,627]	add migrate task: E:\cloud\vod_migrate\media\测试.png
[2020-06-23 11:03:17,772]	当前迁移进度:16.67%,总量:6,成功数:1,失败数:0
[2020-06-23 11:03:17,852]	当前迁移进度: 33.33%, 总量: 6, 成功数: 2, 失败数: 0
[2020-06-23 11:03:17,957]	当前迁移进度: 50.00%, 总量: 6, 成功数: 3, 失败数: 0
[2020-06-23 11:03:18,068]	当前迁移进度:66.67%,总量:6,成功数:4,失败数:0
[2020-06-23 11:03:18,218]	当前迁移进度: 83.33%,总量: 6,成功数: 5,失败数: 0
[2020-06-23 11:03:18,292]	当前迁移进度:100.00%,总量:6,成功数:6,失败数:0
[2020-06-23 11:03:19,295]	tasks finished
[2020-06-23 11:03:19,454]	migrate result: E:\cloud\vod_migrate\vod_migrate_result.txt

Live Recording Recording to VOD and Processing Video

Last updated : 2023-05-15 17:37:30

Live recording is a solution that records and saves live streams to VOD after remuxing (without modifying audio/video data, timestamp etc.). The recording files can be further processed and distributed. For details, see Live Recording.

Strengths

Based on the capabilities of CSS, the live recording feature can quickly record and store live streaming content to VOD for secondary production and distribution.

Relying on Tencent Cloud's leading AI technologies in audio and video and globally deployed cache nodes, VOD provides top-notch audio/video services including stream publishing, transcoding, distribution, and playback, delivering ultra-low latency and ultra-high image quality while being capable of handling large numbers of concurrent requests.

With the live recording feature, you can easily spread videos of your live events in various scenarios and to different applications.

The feature is useful in cases such as corporate live streaming, live shopping, and online classes. It allows you to distribute your content through different channels.

Prerequisites

You have signed up for a Tencent Cloud account and logged in. You have activated CSS and VOD.

Directions

Step 1. Create a recording template

To use the live recording feature, you need to create a recording template first. The configuration of live recording is saved in the recording template. You can create recording templates with different configurations to record files into different formats or different durations.

Creating a template in the console:

1.1 Log in to the CSS console and select Feature Configuration > Live Recording.



1.2 Click **Create Recording Template** and select at least one recording format. For detailed directions, see **Creating** a Recording Template.

	Recording Configu	iration		
443	Template Name *	Enter a template name		
test0825		Only support letters, digits, underscores, ar		
test	Template Description	Please describe template		
recordchenhui				
All_Formats		Only support letters, diaits, underscores		
	Recording Format *	HLS FLV MP4 AAG		
		▼ Audio/Video - MP4		
		Max Recording Time 1-120 Per File		
		Storage Period O Permanent		
		VOD Subapplication/Cate		

1.3 Click Save.

Creating a template using an API:

You can also call the CreateLiveRecordTemplate API to create a recording template. The template ID will be returned after the template is created successfully.

Step 2. Select a recording scheme

CSS offers the following recording schemes for different scenarios:

Scheme 1. Global recording for a domain name

You can bind your live recording template to a push domain in the CSS console or by calling an API, and streams pushed through the domain will be recorded automatically.

Use cases: Showroom streaming, live shopping, online classroom, and video surveillance.

Steps:

1.1 After creating a recording template, you will be prompted to bind a domain name. Click **Bind Domain Name** and select a push domain.

	test1026	
Template ID	54	
		×
Created the Te	mplate Successfully	
Bind an CSS domain	name and then you can use this template for record	ding. Or you
can select a domain	name in Domain Management and manage the reco	ording

1.2 You can also bind a push domain on the **Domain Management**. Click your push domain. On the domain details page, select **Template Configuration**. In the **Recording Configuration** area, click **Edit** to bind the push domain. For more information, see <u>Binding a Recording Template</u>.

Domain Manag	ement / 🚛		
Basic Info	Push Config	guration Te	emplate Configuration
		 Recording, w current live s 	vatermarking, screencapture & porn detection are value-added services. B streaming, and will take effect after you restart the push .
		Recording Conf	figuration
		Template Name	None
		Template ID	None
		Recording Format	None

1.3 Alternatively, you can call CreateLiveRecordRule, passing in the template ID and push domain to bind them.

Scheme 2. Recording a specified stream

You can record a specific live stream by binding your live recording template to the specified live stream through an API.

Use cases: Live events, live exhibitions, sports live streaming, and co-streaming.

Steps: To bind a recording template to a specific live stream, call CreateLiveRecordRule, passing in the recording template ID, the target push domain, push path, and StreamName (these three parameters must match).

Scheme 3. Recording a specified time period

You can call an API to specify the time to start and end recording.

Use cases: News live streaming and live events.

Steps: Call CreateRecordTask to create a recording task, specifying the recording template ID, the target push domain, push path, and StreamName (these three parameters must match), as well as the start and end time. **Example**:

1. In the simplest case, you only need to specify StreamName , DomainName , AppName , and EndTime to record live streams.

The following sample code creates a video recording task from 8 AM to 10 AM on August 10, 2020. The recording files are in FLV format and are saved permanently. Each segment is 30 minutes long.

Sample request:

https://live.tencentcloudapi.com/?Action=CreateRecordTask&AppName=live&DomainName=m

2. You can also specify the recording format, recording type, and storage parameters.

The following sample code creates a video recording task from 8 AM to 10 AM on August 10, 2020. The recording



files are in MP4 format and are saved permanently. Each segment is one hour long.

3. Call CreateLiveRecordTemplate to create a recording template.

Sample request:

```
https://live.tencentcloudapi.com/?Action=CreateLiveRecordTemplate&TemplateName=temp
```

Sample response:

{"Response": {"RequestId": "839d12da-95a9-43b2-a9a0-03366d01b532", "TemplateId": 170

4. Call CreateRecordTask to create a recording task.

Sample request:

https://live.tencentcloudapi.com/?Action=CreateRecordTask&StreamName=livetest&AppNa

Scheme 4. Real-time recording (mixed-stream recording is supported)

You can record any segment of a stream in real time through API calls.

Use cases: Scenarios where only segments need to be recorded, such as sporting events or game live streaming (you can also record streams globally and clip out the segments you need afterward).

Steps: Call CreateRecordTask to create a recording task, specifying the recording template ID, the target push domain, push path, and StreamName (these three parameters must match), as well as the end time. The task will start immediately after creation.

Example:

https://live.tencentcloudapi.com/?Action=CreateRecordTask&StreamName=test&AppName=1

Scheme 5. Audio-only recording

If only audio is published, you can record it in AAC format.

Use cases: Audio live streaming and audio co-streaming.

Steps: When creating the recording template, select AAC as the format, and bind the push domain.

Note:

A binding rule will take effect in about **5-10 minutes** after creation. Any change of the binding rule will not affect live streams that are being pushed and will apply only to new streams.

Step 3. Publish a stream

After binding the recording template with your push domain as instructed in Step 2, generate a push address using the push domain, and push you stream via the address.

After the live stream ends, the recording file will be stored to VOD.

Note:



If you have selected a subapplication when creating the recording template, the recording file will be stored in the specified subapplication.

If you want to receive the URL of the recording file via a callback, you need to create a callback template (enter the callback URL and bind the push domain) before publishing your stream. For details, see Recording Event Notification.

Step 4. Get the recording file

You can query and get a recording file using the following methods:

Recording callback: If you have configured a callback template (you need to provide a callback URL) before publishing a live stream, when a recording file is generated, a callback will be sent to your callback server. To learn more, see Recording Event Notification.

Create Callback Template Bind	I Domain Name		
test		Callback Configuratic	n
		Template Name *	test
			Only support letters, digits, underscores, and dashes
		Template Description	Please describe template
			Only support letters, digits, underscores, and dashe
		Callback Key	Enter a callback key (composed of uppercase and
		Push Callback	Enter a push callback URL (header: http, https, etc
		Interruption Callback	Enter an interruption callback URL (header: http, h
		Recording Callback	http://.
		Screencapture Callback	Enter a screencapture callback URL (header: http,
		Porn Detection Callback	Please enter a porn detection callback URL (heade
			Save

VOD console: You can query a recording file in the VOD console. For more information, see View Audio/Video Files. **VOD API**: You can also call the SearchMedia API to query files.

Step 5. Process the recording file

Scheme 1. Live recording + automatic transcoding + video playback acceleration

Use cases: The recording file of a live stream can be immediately transcoded and accelerated automatically for viewers to play back on demand. This scheme is suitable for most live streaming scenarios where no video processing is required.

Steps:

1.1 When creating a recording template before stream publishing, click **Advanced Configuration** to configure a task flow.

Create Template	Recording Configu	ration		
	incortaing conligu			
	Template Name *	Enter a template name		
-		Only support letters, digi	ts, underscores, and dashes.	
	Template Description	Please describe templa	ite	
m.				
		Only support letters, digi	ts, underscores, and dashes.	
	Recording Format *	HLS FLV	MP4 AAC (i)	
		▼ Audio/Video - HLS		
		Max Recording Time Per File	No time limit	
		Resumption	1-1800	
		limeout	This value will affect when to genera	ate
		Storage Period	O Permanent Custom	
		VOD	Primary application	r
		Subapplication/Cate gory		

1.2 Bind the template to a video processing task flow you created in the VOD console.



You can click a task flow t	o go to the VOD conso	le to add	/modify its	settings, and	refresh ^k
Name				Task	Flow T.
C LongVideoPreset				Prese	et
SimpleAesEncrypt	Preset			Prese	et
Total items: 2	10 🔻 / page		1	/ 1 page	
After the template is bou files are generated, which	nd with a VOD task flov incurs VOD costs. For	v, the flow detailed p	v will be ex pricing, see	ecuted after re VOD Billing O	ecording verview

1.4 After recording is finished, get the file ID from the callback.



1.5 Get the URL of the recording file for playback.

Scheme 2. Live recording + manual transcoding + video playback acceleration



Use cases: If you want to record live streams to VOD without transcoding the recording files right away, do not add a task flow when creating the recording template. When you want to transcode the videos later, you can do it manually. You can also use the on-cloud clipping feature to clip the recording files.

Steps:

1.1 Publish the live stream. For details, see Live Push.

- 1.2 The stream will be automatically recorded to VOD.
- 1.3 Get the file ID.

1.4 Configure a transcoding template or task flow manually to transcode the recording file. For details, see Template Settings.

T 1 51 N							
lask Flow Name	Enter task flow name						
	It should be a combination of lett	ers, numbers, hyphens (-), and	underscores (_) with a len	gth up to 20 chars			
Task flow Description	Please describe task flow						
	Up to 15 chars for description						
Configuration Item	General Transcoding	ESHD Transcoding Ren	ux Adaptive Bitra	te Streaming Scre	enshot Task Capt	ure Cover Task 📃 Dyi	namic Image Task
	Select at least one configuration i	tem					
You can go to "Templat	te Settings - Transcoding Template "	to create a transcoding templa	te, and go to "Template ! Video Encoding	Gettings -> - Watermar Video Bitrate	k " to create a watermark	template. After creation,	click here to Purge,
You can go to "Templat Transcoding	te Settings - Transcoding Template " Template/ID	to create a transcoding templa	te, and go to "Template s	Settings -> - Watermar Video Bitrate	k " to create a watermark Resolution	: template. After creation, · Frame rate	click here to Purge, Audio Encoding
You can go to "Templat	te Settings - Transcoding Template " Template/ID	to create a transcoding templa Encapsulation For	te, and go to "Template ! Video Encoding Ti	iettings -> - Watermar Video Bitrate ne current list is empty	k " to create a watermark Resolution	template. After creation, - Frame rate	click here to Purge, Audio Encoding
You can go to "Templat Transcoding Add transcoding tem	te Settings - Transcoding Template " Template/ID nplate	to create a transcoding templa	te, and go to "Template Video Encoding Ti	Settings -> - Watermar Video Bitrate ne current list is empty	k " to create a watermark Resolution	template. After creation,	click here to Purge, Audio Encoding
You can go to "Templat Transcoding " Add transcoding tem	te Settings - Transcoding Template " Template/ID nplate	to create a transcoding templa	te, and go to "Template ! Video Encoding Ti	iettings -> - Watermar Video Bitrate ne current list is empty	k " to create a watermark Resolution	template. After creation, - Frame rate	click here to Purge, Audio Encoding
You can go to "Templat Transcoding " Add transcoding tem	te Settings - Transcoding Template " Template/ID nplate	to create a transcoding templa	te, and go to "Template ! Video Encoding Ti	iettings -> - Watermar Video Bitrate ne current list is empty	k " to create a watermark	template. After creation,	click here to Purge, Audio Encoding

1.5 You can further edit the videos if necessary.

1.6 After transcoding and processing, get the URL of the output file for playback.

Scheme 3. Live recording + adaptive bitrate streaming + video delivery acceleration + player

Use cases: If you have high security requirements that cannot be met by HLS encryption, you can use adaptive bitrate streaming together with our Player SDK. This scheme is suitable for online education and corporate training. **Steps**:

- 1.1 Publish the live stream. For details, see Live Push.
- 1.2 The stream will be automatically recorded to VOD.
- 1.3 Get the file ID.
- 1.4 Configure a task flow to generate adaptive bitrate streams. For details, see Task Flow Settings.

Task Flow Name	Enter task flow name				
	It should be a combination of let	 ters, numbers, hyphens (-), and under	scores (_) with a length up to 20 cl	hars	
Task flow Description	Please describe task flow				
	Up to 15 chars for description				
Configuration Item	General Transcoding	TESHD Transcoding 📃 Remux	✓ Adaptive Bitrate Streaming	Screenshot Task	Capture Cove
	Select at least one configuration	item			
Adaptive bitrate st You can go to "Templat	reaming task configuration	ning Template to view adaptive bitrat	e streaming template. Template cre	eation is not supported	for the moment.
Adaptive bitrate st You can go to "Templat Adaptive Bitr	reaming task configuration e Settings - Adaptive Bitrate Strear ate Streaming Template/ID	ning Template to view adaptive bitrat Muxing Type	e streaming template. Template cro Substream Cour	eation is not supported	for the moment. Switch from l
Adaptive bitrate st You can go to "Templat Adaptive Bitr	reaming task configuration e Settings - Adaptive Bitrate Strear ate Streaming Template/ID	ning Template to view adaptive bitrat Muxing Type	e streaming template. Template cre Substream Cour The current list is	eation is not supported nt s empty	for the moment. Switch from l
Adaptive bitrate st You can go to "Templat Adaptive Bitr Add Template	reaming task configuration e Settings - Adaptive Bitrate Strear ate Streaming Template/ID	ning Template to view adaptive bitrat Muxing Type	e streaming template. Template cro Substream Cour The current list is	eation is not supported nt s empty	for the moment. Switch from
Adaptive bitrate st You can go to "Templat Adaptive Bitr Add Template	reaming task configuration e Settings - Adaptive Bitrate Strear ate Streaming Template/ID	ning Template to view adaptive bitrat Muxing Type	e streaming template. Template cro Substream Cour The current list is	eation is not supported nt s empty	for the moment. Switch from l
Adaptive bitrate st You can go to "Templat Adaptive Bitr Add Template	reaming task configuration e Settings - Adaptive Bitrate Strear ate Streaming Template/ID	ning Template to view adaptive bitrat Muxing Type	e streaming template. Template cre Substream Cour The current list is	eation is not supported nt s empty	for the moment. Switch from

1.5 Configure the player: Select the adaptive bitrate stream generated for playback.

Adaptive bitrate streaming template for playback					
You can go to "Template Settings - Adaptive Bitrate Streaming Template" to create a Adaptive bitrate streaming template. After creation, click Purge Adaptive Bitrate Streaming Template/ID Encryption Type Muxing Type Substream C					
Adpative-HLS(10)	Not encrypted	HLS	6		

1.6 Play the video by specifying the file ID.

Live Streaming Time Shifting

Last updated : 2024-10-12 10:22:55

Combining the time shifting feature of CSS and the delivery acceleration capability of VOD, time shifting for live stream playback allows users to rewind and play back earlier parts of a live stream. This is commonly used to play back highlights during live streamed sports events. Users can drag the progress bar to view earlier parts of a live stream, and they can also switch back to continue viewing the currently ongoing live stream.

Strengths

Users can specify the delay for playing live content, i.e., the difference between the playback start time and current time.

Users can specify the bitrate for time shifting if a live stream is recorded in multiple bitrates.

Prerequisites

You have signed up for a Tencent Cloud account and logged in. You have activated CSS and added a push domain.

Must-Knows

Before you can use the time shifting feature, you must first enable the feature for a stream.

Currently, the smallest time-shift offset is 90 seconds, which means there must be a delay of at least 90 seconds between live content and time-shifted content.

Time shifting relies on the live recording feature. Therefore, you may also incur VOD storage and traffic costs.

Directions

Step 1. Activate VOD

- 1. Go to the VOD console. Click Activate Now.
- 2. Agree to the service agreement, and click OK to activate VOD.

Step 2. Add a domain for time shifting

Follow the steps below to add a VOD domain for time shifting:



1. Log in to the VOD console. Select **Application Management** on the left sidebar and select the target application. Go to **Distribution and Playback > Domain Name**.

2. Click Add Domain and enter a domain name. For detailed directions, see Distribution and Playback Settings.

VOD	← Add Domain	Primary application •	
Service Overview			
▶ Media Assets ×	Domain Name Conf	iguration	
Task Management	Domain Name	Enter name	
📀 Video Audit	Acceleration Region (j)	O Chinese mainland (ICP filing req	uired) Outside Chinese mainland (ICP filing not re
System Settings	C		
🐼 Video Processing 👻	Confirm	ncei	
Distribution and ^ Playback			
· Domain Name			

3. Add a CNAME record for the domain.

Step 3. Bind a recording template

- 1. Go to the CSS console and select Feature Configuration > Live Recording.
- 2. Click Create Template. For detailed directions, see Live Recording.

mplate Name *	Enter a template name					
	Only support letters, digi	its, underscores, and dashes.				
emplate Description	Please describe templa	ite				
	Only support letters, digi	its, underscores, and dashes.				
ecording Format *	HLS FLV	MP4 AAC (i)				
	 Audio/video - HLS 					
	Max Recording Time Per File	No time limit		min		
	Max Recording Time Per File Resumption Timeout	No time limit 1-1800		min sec		
	Max Recording Time Per File Resumption Timeout	No time limit 1-1800 This value will affect when	to generate	min sec	ding file.	
	Max Recording Time Per File Resumption Timeout Storage Period	No time limit 1-1800 This value will affect when O Permanent Cust	to generate om	min sec	ding file.	
	 Audio/Video - HLS Max Recording Time Per File Resumption Timeout Storage Period VOD Subapplication/Cate gory 	No time limit 1-1800 This value will affect when Permanent Cust Primary application	to generate om	min sec a record	ding file. s	

Note:

Select HLS as the file format.

Set the file storage period, which cannot be shorter than the time-shift period.

3. Bind the recording template to the push domain. For detailed directions, see Recording Configuration.

Step 4. Enable time shifting

You need to submit a ticket to enable the time shifting feature: Select "CSS", make your request, and provide the following parameters:

The domain added in Step 2.

The ID of the recording template created in Step 3.

```
The time-shift period ( timeshift_dur ) in seconds.
```

Note:

Time-shift period indicates how further back you can go in terms of time shifting. The maximum time-shift period allowed currently is 7 days.

This feature may not work exactly according to the period configured. We recommend you set the period a little longer than you actually need.

If the time-shift period is set to 7200 (two hours), you will be able to request content generated as early as two hours ago. (i.e., the value range for playback delay is 90 seconds to 2 hours). If content generated earlier than two hours ago is requested, HTTP 404 will be returned even if there is live streaming content at the requested time.

Playback Request

Request URL format

```
http://[Domain]/timeshift/[AppName]/[StreamName]/timeshift.m3u8?delay=xxx
```

Parameter description

Parameter	Description
[Domain]	The domain you registered for time shifting (the domain you added in the VOD console).
timeshift	This is a fixed field. You don't need to modify it.
[AppName]	The application name. For example, if your application is named live , pass in live .
[StreamName]	The stream name.
timeshift.m3u8	This is a fixed field. You don't need to modify it.
delay	The playback delay (seconds). This parameter cannot be smaller than 90. If you pass in a value smaller than 90, 90 will be used.

Example

Suppose the time-shift domain name is testtimeshift.com , application name live , and stream name SLPUrIFzGPE . If you need to play back live content generated 5 minutes ago, the request URL should be: http://testtimeshift.com/timeshift/live/SLPUrIFzGPE/timeshift.m3u8?delay=300

How to Make VOD Videos Live Streaming-Like

Last updated : 2023-05-15 17:38:25

Based on its playback control capability, VOD can add access controls of "playback time constraint" and "syncing playback progress" to VOD files to implement pseudo-live streaming. This allows you to distribute VOD videos as live streams at the scheduled time, thus saving costs and avoid the risks associated with live streaming.

Strengths

Benefit	Description
Low development costs	To convert a VOD video to a common live stream for delivery, you need to use OBS to publish the video to the live streaming platform and deal with the compatibility issues by yourself. This incurs high development costs. VOD can implement pseudo-live streaming automatically for you. You only need to enable transcoding and hotlink protection.
Low compliance risks	You can moderate and edit VOD files in advance to avoid the risk of non-compliance.
Ease of use and flexibility	No live streaming rooms are needed and any videos can be used for pseudo-live streaming. There is no upper limit on concurrency. You can specify a start time for pseudo-live streaming and share the playback URL beforehand.

Use Cases

This feature is mainly used in scenarios where videos need to be recorded beforehand and viewed by users concurrently at a preset time. Viewers can get the playback URL in advance but cannot watch the video before the preset time.

In pseudo-live streaming, viewers cannot change the playback speed. It is commonly used to stream online classes, concerts, and TV shows.

Must-Knows

Use limits
Because pseudo-live streaming is essentially on-demand delivery, it lacks some capabilities of a real live stream:

You cannot collect statistics for a pseudo-live streaming session.

There is no clear indication of the start and end of a pseudo-live streaming session.

You cannot pause/terminate an ongoing pseudo-live streaming session.

You cannot block a pseudo-live streaming URL that has been distributed.

You cannot dynamically change the video content (such as real-time transcoding and watermarking).

Glossary

Allowed watch time: A video URL can be provided to viewers in advance, but the content is not accessible before the specified start time or after the specified end time.

Synced viewing: During a pseudo-live streaming session, all viewers watch synchronously with the same progress (there may be a difference of a few minutes).

Prerequisites

You have signed up for a Tencent Cloud account and logged in.

You have activated CSS and VOD.

You have recorded a live stream. For detailed directions, see Recording to VOD and Processing Video.

Directions

Step 1. Upload a video to VOD

- 1. Log in to the VOD console and select **Application Management** on the left sidebar.
- 2. Select the target application.
- 3. Go to Media Assets > Video/Audio Management and click Upload.



You can also use other upload methods. For details, see Media Upload Overview and Recording to VOD and Processing Video.

Step 2. Transcode the video to HLS

1. Videos for pseudo-live streaming must be in HLS format. You can follow the steps in Transcoding Task Initiation to transcode an uploaded video into HLS format (choose a transcoding template that fits your needs).

2. After the transcoding is finished, you can view the URL of the HLS file generated on the Video/Audio Management of the console or get the URL via event notifications.

 Video Manager Basic Info Screenst 	ment Primary app not Info Superplay	ver Preview We	eb player code gener	ration	
	Basic Info				
	Video Cover				Size
	Video Cover Address	Copy Cover URL			Res
	Video Name	à		1	Cat
	ID Status	3 Normal			Tag Des
	Creation Time	2021-10-12 11:43:0	08		Stor
	Last updated	2021-11-03 09:46:4	14		Ope
	Standard Transco	ding List			
	Specification	1	Format	Resolution	Bitrate
	STD-H264-H	.S-360P	HLS	640 x 360	273.17Kbps

Step 3. Enable key hotlink protection

Hotlink protection is required for pseudo-live streaming. To enable hotlink protection, go to the VOD console. Click
 Application Management on the left sidebar and select the target application. Go to Distribution and Playback >
 Domain Name, find your domain, and click Set on the right.

VOD	Domain Management	Primary application		
Service Overview		Add Domain		
Media Assets		Domain Name	Status	CNAME (j)
 Video Audit 		Default Distribution Domain	€Enable	1
System Settings		Total items: 1		
Distribution and ^ Playback		FAQs:		
Domain Name		Domain Name Guide	CNAME Guide	

2. Under the Access Control tab, enable referer hotlink protection or key hotlink protection.

test.com	📚 test 📼 Su
Basic Configuratio	n Access Control
Referer Hotlink	Protection
Referer Hotlink No Referer hotl	Protection Trule set.
Key Hotlink Pro	otection
Key hotlink protecti	ion URL carries video playback control parameters. For details, see Key Hotlink Protection 🗳 Key Hotlink Protection URL Ge
Key Hotlink Pro	
No key notilik	protection rule set.
Certificate Man	agement
The domain name f applied to all servic	for which you configure the certificate must be connected to Tencent Cloud CDN, and the domain name status must be "de e regions of the selected domain name. For details, see Billing Documentation .
Use Certificate	
No certificate is	; configured.

3. For details on how to configure hotlink protection, see Setting Hotlink Protection. After the configuration, save the key for calculating the hotlink protection signature.

← 100	Primary application	▼ S
Basic Configuration	Access Control	
	Referer Hotlink Protection The HTTP Referer header is used for source identification	and authentication. For details, see Referer Hotlink Pr
	Referer Hotlink Protection No Referer hotlink protection rule set.	Enable Referer Hotlink Protection
	Key Hotlink Protection	 No need to enter "http://". Use "Enter" to sep domain name per line without duplication. If "Allow Empty Referer" is not checked and t protection is not enabled.
	Key hotlink protection URL carries video playback contro Key Hotlink Protection	Referer Type • Allowlist · Blocklist
	No key hotlink protection rule set.	Enter domain names, such as w in the beginning, such as *.test.c
	Certificate Management	
	domain name. For details, see Billing Documentation	Confirm
	Use Certificate	

Step 4. Calculate the hotlink protection signature

Signature calculation formula

sign = md5(KEY + Dir + t + plive + exper + rlimit + us)

Note:

Compared with standard key hotlink protection, hotlink protection for pseudo-live streaming has an additional

parameter plive, which is also included in the signature calculation formula.

Parameter	Value	Description
KEY	11111111	The key you set when enabling key hotlink protection.



Dir	/dir1/dir2/	The part of the original video URL with the filename myVideo.mp4 removed.
t	5a71afc0	The expiration timestamp (1517400000) converted to hexadecimal.
plive	5e344f00	The start time (UTC+8) of the pseudo-live streaming session, in Unix timestamp format. For example, 1577808000 means 00:00:00 on January 1, 2020.
exper	0	The preview duration. 0 means no limit will be set.
rlimit	0	The number of IP addresses allowed to play the video. 0 means no limit will be set.
us	test	The generated random string.

Suppose you have a video stored in VOD, and the URL of its HLS-format file (not the original video URL) is

```
http://125000000.vod2.myqcloud.com/vodtranscq125000000/12345678/v.f240.m3u8 .The
other parameters are as follows:
Hotlink protection key: 1111111 .
Expiration time ( t ): 5e5a8a80 (March 1, 2020 00:00:00).
Start time ( plive ): 5e344f00 (February 1, 2020 00:00:00).
Preview duration ( exper ): 0 (no limit).
Maximum number of IP addresses allowed ( rlimit ): 0 (no limit).
```

Random string (us): test .

1. Calculate the signature based on the signature calculation format:

sign = md5(11111111/vodtranscq125000000/12345678/5e5a8a805e344f0000test) = 0af5018d

2. Add the signature generated to the query string of the HLS URL to get the final hotlink protection URL:

http://1250000000.vod2.myqcloud.com/vodtranscq125000000/12345678/v.f240.m3u8?t=5e5a

Note:

The parameters in the query string must be in the same order as when sign is calculated, which is t-plive-exper-rlimit-us-sign .

To facilitate your development, we provide a hotlink protection signature generation tool. Just enter the necessary parameters, and you will get the signature and the final hotlink protection URL.

Watching Pseudo-Live Streaming



Open the above hotlink protection URL in a player that supports HLS playback (such as Safari, VLC, and PotPlayer) to watch pseudo-live streaming.

Note:

Chrome does not support HLS playback. You need to install a plugin.

Using VOD and WordPress to Build a Website

Last updated : 2022-11-02 16:27:12

Overview

WordPress is a popular open-source blog framework and content management system. It can significantly reduce the difficulty and increase the efficiency of website building. Using WordPress plans, you can get a small website up and running in just a few minutes. However, as you add images, audios, and videos to your WordPress website, it will become more and more demanding on bandwidth and storage, which may start to affect your website's performance. The management of media files is crucial to the long-term success of a website.

Why VOD

We do not recommend using WordPress' default features to upload videos directly to a WordPress website that you intend to run long term. This is mainly because the media files are stored in a web server, which has the following disadvantages:

No.	Disadvantages
1	When users access media files hosted in a web server, videos may stutter and images may be slow to load.
2	Accessing media files hosted in a web server consumes bandwidth resources and may take up all your bandwidth.
3	As your website grows, media files may take up all the server's storage space.
4	When you migrate to a different server, the transfer of media files can be cumbersome.

VOD offers media storage, transcoding, and distribution/playback acceleration services. Using it to build your website has the following advantages:

No.	Advantages
1	Using our WordPress plugin or SDK, you can upload and store your website's media files to VOD. This can free up storage space in the server and facilitate easier server migration. It also avoids the problem of deleting files by mistake.
2	VOD offers CDN addresses for your media files, which makes accessing images, audios, and videos faster and does not consume your server's bandwidth.



VOD also offers access control, media processing, and content moderation capabilities. For details, see Feature Overview.

VOD plugin

VOD offers a WordPress plugin. Using this plugin, you can bind a VOD subapplication to host your WordPress media files in VOD. Visitors of your website can access the files via the CDN addresses provided by VOD. Currently, the plugin can achieve the following:

You can bind a VOD subapplication to WordPress.

The video files you upload to WordPress can be automatically saved to the VOD subapplication.

If you embed a video on a webpage, the video will be played via the address offered by VOD.

Prerequisites

1. Create a VOD subapplication

VOD supplications help you achieve resource isolation. You can bind different websites to different VOD subapplications so that you can manage their media files separately. To learn about how to create a subapplication, see Subapplication System.

2. Use WordPress to build a website

You can build a WordPress website in one of the following two ways:

Method 1 (recommended)

Method 2

Use the WordPress image of TencentCloud Lighthouse or Cloud Virtual Machine to build a website.

Download and install the latest version of WordPress. For detailed directions, see How to install WordPress.

Directions

Step 1. Install the plugin

Install online Download and install Type **tencentcloud-vod** in the search box, click **Install**, and then click **Activate**.

🕸 Dashboard	Add Plugins Upload Plugin
🖈 Posts	
9) Media	Search Results Featured Popular Recommended Favorites Keyword V tencentcloud-vod 2
Pages	
Comments	
🔊 Appearance	
🖆 Plugins 🌖 🛛 🖌	Install Now More Details
Installed Plugins Add New Plugin File Editor	Cloud
👗 Users	★★★☆☆☆(2) Last Updated: 1 week ago
🖋 Tools	50+ Active Installations Untested with your version of
E Settings	WordPress
Collapse menu	

Download a ZIP file of the latest version of the plugin. In WordPress, click **Upload Plugin > Choose File > Install Now**. After the installation, click **Activate**.

£	Dashboard	WordPress 6.0.1 is available! Please update now.
ォ	Posts	
9,	Media	Add Plugins Upload Plugin 2
۲	Pages	
•	Comments	If you have a plugin in a .zip format, you may install or update it by uploading it here
×	Appearance	
<u>k</u> e	Plugins 🚹 🛛 🧹	
Ins	talled Plugins	choose file tencentcloud-ws-plugin-vod.zip Install Now
Ad	d New 🚺	<u> </u>
Plu	ıgin Editor	
*	Users	
رعو	Tools	Factured Description Description - Manual - Description
53	Settings	Regword V Search plugins
0	Collapse menu	Plugins extend and expand the functionality of WordPress. You may automatically install plugins from the WordPress I

Step 2. Configure the plugin

In WordPress, select **Tencent Cloud Settings > VOD** on the left sidebar.



Complete the following settings:

Item	Description
Custom key	If you toggle this off, the key configured for Tencent Cloud Settings will be used, which means the VOD plugin will use the same key as other Tencent Cloud plugins. If you toggle this on, the key configured below will be used.
SecretId, SecretKey	The access key. You can go to the API Keys page of the console to create and view access keys.
SubAppID	The ID of the VOD subapplication you want to bind. You can view your VOD subapplications in Application Management.
Adaptive bitrate	If you toggle this on, videos uploaded will be encoded at multiple bitrates. For details, see Adaptive Bitrate Streaming.

Click Save.

3. Upload videos and use VOD videos in your webpage

1. After you finish configuring the plugin, the videos in the media library of WordPress as well as the videos you upload while editing a post or webpage will be automatically saved to VOD.

2. For example, when you edit a post in WordPress, click the plus icon, select **Video**, and click **Upload** to upload a video. After the video is uploaded, click **Preview** in the top right corner. You will see that the video is played via VOD's URL.





3. As you can see below, the video on the left is stored in a web server, which stutters due to limited bandwidth. This is not a problem if you use VOD, which uses its CDN to accelerate video distribution.



Others

Using HTTPS



VOD uses HTTP by default. If you want to use HTTPS, select your subapplication in the VOD console, go to **System Settings > Distribution and Playback > Default Distribution Domain**, click **Edit**, and select **HTTPS** for **Default Distribution Protocol**.

How to Pull from Custom Origin Servers

Last updated : 2023-03-07 15:49:29

Overview

You can configure a third-party origin server for your domain in VOD to pull media files from the origin server and distribute the media via VOD. This multi-cloud media distribution solution is enabled by VOD's CDN capability. This document shows you how to configure and use an origin server with VOD.

Use cases

Your media assets are stored with a third-party cloud vendor, and **the cost of migrating them is high**. You can use VOD's custom origin server feature to deliver your content without migrating your media assets. You have **high requirements on latency and stuttering** and your existing service provider is unable to meet them. You can use VOD's custom origin server feature to deliver smoother playback and improve your user experience. You need **more than one channel** to distribute your content to ensure the reliability and improve the disaster recovery capability of your business.

Prerequisites

1. You have signed up for a Tencent Cloud account, completed identity verification, and logged in.

2. You have activated VOD.

Supported Origin Server Types

Self-owned origin servers Third-party storage services

Directions

Step 1. Add a domain and configure origin server information

1. Log in to the VOD console and select **Distribution and Playback** > Domain Name on the left sidebar.

2. Select the **Custom origin server domains** tab at the top.

VOD accel	eration domains Custom origin server doma	ains		
	 Custom distribution domains give you great 	ter flexibility.		
	 To prevent your traffic from being stolen, we 	e recommend you enable hotlink protection in "	Access Control" of the "Domain Manager	ment" page. <u>Learn about ho</u>
	After hotlink protection is enabled, only URI	Ls that include the hotlink protection signature	can be used for playback. How to enable	key hotlink protection
	 Only custom domains support distribution fro 	om third-party origin servers. Such a domain ca	nnot be set as the default distribution dor	nain.
	Add Domain			
	Domain Name	Status	CNAME (Domain Name Type
	<u>A</u>	Configuring		Custom Domain Nam
	Total items: 2			
	FAQs:			
	Custom origin server guide	CNAME G	uide	
	How to configure a custom origin server domain?	What is CN/	MME?	
	What is a custom origin server domain?	What is a Cl	NAME record?	

3. Click Add Domain and enter a domain. For more information, see Customizing Domain Names.

guration			
O Chinese mainland (ICP filing required	Outside Chinese mainland (ICP filing not required)	Global acceleration (ICP filing required)	
	Chinese mainland (ICP filing required)	Enter name Chinese mainland (ICP filing required) Outside Chinese mainland (ICP filing not required)	

4. Enter your origin server information. Currently, **self-owned servers** and **third-party storage** are supported.

Origin server (j)	
Origin server type	Self-owned server Third-party storage
Protocol	O HTTP HTTPS Same as request (
Origin server address	You can enter multiple IP addresses (separate with commas) or one domai
Host 🛈	Optional
Confirm Car	

Self-owned servers

If you want to use your existing server as the origin server to distribute media files stored in it via VOD, configure as follows:

Item	Description
Origin server type	Select Self-owned server
Protocol	Select the protocol, which can be HTTP, HTTPS, or "Same as request".
Origin server address	You can enter multiple IP addresses (separate with commas) or one domain.
Host	For self-owned origin servers, you can specify the host of a domain or IP address that VOD pulls from. If you do not specify it, VOD will pull from the current domain.

Note:

You cannot use your VOD default domain as the origin server address.

If you select **Same as request**, HTTP will be used for HTTP requests, and HTTPS will be used for HTTPS requests (your origin server must support HTTPS).

You can use a domain as the origin server address, but this domain cannot be the same as the domain you use for acceleration.

Third-party storage

If you want to distribute the media files you store in a third-party storage service via VOD's CDN, configure as follows:

Item	Description
Origin server type	Select Third-party storage
Third-party storage	Currently, Alibaba Cloud OSS and AWS S3 are supported.

Protocol	HTTP or HTTPS
Origin server address	Enter a valid bucket address (cannot contain "http://" or http:// headers).

Modify origin serve	r settings
Origin server type	Self-owned server O Third-party storage
Third-party storage	Qiniu Cloud Baidu Cloud Alibaba Cloud O AWS
Protocol	
Origin server address	
Private bucket access	Grant access If you use a private bucket as the origin server, you need to grant VOD access to that bucket.
Host (j)	Optional
	Confirm

If you use a private bucket as the origin server, you need to enter a valid access ID and key to authorize VOD to access the bucket.

 Make st 	ure you enter a valid access ID and key.	
 For sect However 	urity reasons, you cannot view the key after you submit the information. er, you can modify it.	
• To prote	ect your account, we recommend you configure permission-based key	
	tion at your vendor How to use a third-party storage service as the origin	
distribut server?	tion at your vendor. <u>How to use a time party storage service as the origin</u>	
distribut <u>server?</u>	torrat your vendor. <u>How to use a trind party storage service as the origin</u>	
distribut server?	torrat your vendor. <u>rrow to use a trind party storage service as the origin</u>	
distribut <u>server?</u> Access ID		
Access ID Access key		
Access ID Access key		

Step 2. Configure CNAME for your domain

After you add a custom domain in VOD, you need to add a CNAME record for it at your DNS provider before users can access your media files via the domain. For detailed directions, see Configuring CNAME.

Step 3. View and modify origin server information

1. Go to Domain Name, select the Custom origin server domains tab, find the domain you added, and click Set.



VOD acceleration dom	ains Cus	tom origin server domai	ns			
0	Custom distribu To prevent your After hotlink pre	ution domains give you greater traffic from being stolen, we re stection is enabled, only URLs	flexibility. scommend you enable hotlink ; that include the hotlink protect	protection in "Access on signature can be u	Control" of the "Domain Manage used for playback. <u>How to enable</u>	ment* page. <u>Learn about h</u> <u>> key hotlink protection 12</u>
0	Only custom dom	nains support distribution from	third-party origin servers. Such	a domain cannot be	set as the default distribution do	main.
Add D)omain					
Domain	Name		Status		CNAME (Domain Name Type
۵ –	com		Configur	ng		Custom Domain Nar
Total ite	ms: 2					
FAQ	5					
Cust	om origin serv	ver guide		CNAME Guide		
How t	o configure a cus	tom origin server domain?		What is CNAME?		

2. Click **Basic Configuration** to view or modify the origin server settings of the domain.

shishi.c	om	
Basic Configu	Access C	Control
	 ICP filing is req By default, VOI After you add a Each account of 	uired if a domain is used to distribute content in the Chinese mainland. <u>Applying for an ICP filing</u> D distributes content stored in VOD. If you use a third-party origin server, you may be charged additional fees by your vendor. <u>Custom origin serve</u> I domain or modify the settings of a domain, it takes about 5–10 minutes for the domain or new settings to take effect. You can view the status, C can add at most 20 domains
	Basic Info	
	Domain Name	
	CNAME	
	Creation Time	2023-01-12 19:17:08
	Acceleration Region	Outside Chinese mainland Modify
	Origin server	
	Origin server type	
	Protocol	
	Origin server address	
	Host	-
	Private bucket access	e

After completing the above steps, you will be able to distribute media files to end users from a self-owned server or third-party storage service via VOD's CDN. The process is as follows:

1. After you complete the above settings for a custom domain (for example test.com), when an end user opens the address of a media file under the domain (for example http://www.test.com/test.mp4) in a browser, a request will be sent to the local DNS resolver.

2. Because a CNAME record (www.test.com.cdn.dnsv1.com) has been added for the domain, the request will be referred to Tencent's proprietary load balancing system Global Server Load Balance (GSLB).

3. GSLB will return a list of IP addresses to the local DNS resolver.

4. The user gets the IP address of the optimal node to access the media file.

5. The end user sends a request to the IP address to visit the media file http://www.test.com/test.mp4 .

6. If the test.mp4 file has been cached in the CDN node, the file will be returned to the user. If not, the node will request the file from the **origin server you configured**, cache the file, and return it to the user.

Note:

Using VOD's origin server feature to distribute media files will incur **playback traffic costs** and **origin server traffic costs**. Playback traffic costs are charged by VOD. For details, see Daily Pay-As-You-Go and Prepaid Packages. Origin server traffic costs are charged by your origin server.

How to Use EdgeOne to Distribute Content in VOD

Last updated : 2024-11-29 17:58:49

This document will introduce how to use EdgeOne to distribute files stored in VOD. While enabling EdgeOne domain protection, it also utilizes VOD's copyright protection capabilities to further enhance the protection of high-quality content.

Overview

If your audio and video content is of high value (e.g., courses, movies, short series, etc.), to prevent it from being pirated, you typically need to upload the content to cloud VOD and use private encryption or DRM encryption solutions to secure the content. Additionally, to avoid traffic abuse, you have configured anti-fraud settings such as usage cap and BOT protection in EdgeOne. Now, you can use EdgeOne domains with anti-fraud configurations to accelerate the distribution of encrypted videos in VOD, achieving a stronger content protection effect.

Prerequisites

- 1. You have signed up for and logged in to your Tencent Cloud account and completed identity verification.
- 2. You have activated the VOD service.
- 3. Refer to the guide "Site Acceleration Quick Start" to complete the site and domain integration.

Directions

Step 1. Add the EdgeOne domain for VOD origin site

1. Log in to the EdgeOne console, click **Site List** in the left menu bar, and click the site to be configured on the site list.

2. On the left navigation bar, click **Domain Name Service** > **Domain Management** to enter the domain name management page, and click **Add domain name** to add a new domain name.

\bigotimes	Tencent Cloud Overvie	ew Products (Cloud Object Storage	Video on Demand M	edia Processing Ser	vice Tencent Cloud EdgeOn	e Cloud Streaming Services	+
	maszteam.com Enabled Site ID:	Oomain Mana	gement	ì	Site settings			
== ==	Site Overview	Domain cor	nfiguration					
~	Basic configuration Domain Name Service	Access mode:	CNAME access Switch	Acceleration are	a:Global (MLC exclu	ded) Switch		
9	Domain Management	Add doma	in name Quick ac	d Batch delete	Batch conf	iguration of certificates		Please enter accelerate
0	Traffic Scheduling	Domain	n name	Extended service	Origin type	Origin settings	Status	CNAME
*	Origin Settings	ionxian	gtest22.maszteam.com		VOD	ionxiangtest	Please add CNAME	ionxiangtest22.maszteam
P Q	Performance and security ③ Site Acceleration	vodpro.	.maszteam.com		VOD	ionxiang_test_pro_	Activated	vodpro.maszteam.com.e
Þ	伊 L4 Proxy伊 Security 	vod.ma	iszteam.com	Dvell []	IP/Domain name	vodtest.maszteam.com	Activated	vod.maszteam.com.eo.d
	⊒ Log Service □ Custom response	wx.mas	szteam.com		Object storag	mas-1301446065.cos.ap	Activated	wx.maszteam.com.eo.dn
	pages Multimedia Services	Total items:	4 , selected items: 0					
	Audio and Video Processing							
	Image Processing							

3. In the domain configuration, enter your acceleration domain, select **VOD** as the origin type, choose VOD application you want to use, and click **Next**.



Domain	> 2 Recommended >	3 Configure CNAME
configuratic Domain name	n configuration(Optional)	
Drigin type	IP/Domain name Object storage origin Origin Group V	OD @ Connect the domain name
Application name	Follow site configuration: Disable Enable Disable	maszteam.com www Connect the subdomain
		www.maszteam.com test
		test.maszteam.com
		Connect the wildcard domain name *.maszteam.com

4. In the recommended configuration, select the audio and video on demand and click Next.



Domain > 2 Rec configuration con	ommended figuration(Optional)	Configure CNAME	
dgeOne recommends enabling the followin peration of your business. Once these con ame, you can view it in the 'Rule Engine'. A ngine' to configure it manually.	ng configurations based o figurations are selected, a Iternatively, you can direc	n different business scenarios to ensure the security a rule will be generated in the 'Rule Engine'. After addi atly Skip this step, After the domain name is added, go	and smooth ing the domair o to the 'Rule
website acceleration	⊘ Details	audio and video on live	📀 Detail
It is suitable for e-commerce, websites, UGC comm scenarios that mainly use small static resources (su pictures and small files).	unities and other business ch as web page styles,	Suitable for accelerating online audio and video live streamin scenarios.	g business
large file download	Oetails	audio and video on demand Media Optimized	⊙ Detail
Applicable to large files, such as game installation p updates, application package downloads and other	ackages, application business scenarios.	Supports audio and video pre-fetching features and allo part of the video content at edge nodes, significantly enhanc smoothness and reducing the time to display the first frame.	ws for caching ing playback
API acceleration Paid Add-on	Oetails	WordPress website development	 ⊘ Detail
Applicable to scenarios where dynamic resources (mainstay, such as account login, order transactions queries.	API interfaces, etc.) are the , API calls, and real-time	Suitable for business scenarios through developmenting web WordPress.	osites with
Enabling API acceleration will activate the smart activate	celeration feature in the rule		

5. In the CNAME access mode, EdgeOne will assign a CNAME address for the domain. You need to configure the CNAME to enable the secure acceleration for the domain. For configuration instructions, please refer to: Modifying CNAME Records. Once the configuration is complete, click **Finish**.



at access requests can be directed to the EdgeOne node for acceleratio
add the records after your modification.
add the records after your modification.

Step 2. Enable Access Control for the EdgeOne Domain (Optional)

Note :

If you do not need to enable access control, you can skip this step.

1. Log in to the EdgeOne console. In the left sidebar, click **Site List**. In the site list, click the site to be configured.

2. On the site details page, click **Site Acceleration** to go to the global site configuration page. Then click the **Rule Engine** > **Create Rule** tab, and select **Add Blank Rule**.

Site Overview	Global Settings	B Rule Engine
Basic configuration	Global configuration effective for all domain(s) under the site	Domain-specific configuration
Domain Name Service	① • The rule engine allows rules to be specified more fine-grained for a subdomain name or request URL. The fine-grained rules take high	her priority than global configuration rules.
 Domain Management 	The rule engine also supports other configurations, including URL Rewriting 2 , Modify HTTP Header 2 and Custom Error Pr For details of configurations and precautions, please see Rule Engine 2	age 🖾 .
Traffic Scheduling		
Origin Settings	Create rule	Search names or comments
Performance and security Image: Site Acceleration	9 rules in total, Newly added rules are placed at the bottom by default. The execution order goes from top to bottom, with lower rules having lower rule will override those specified in the upper rule.	higher priority. This means that if multiple rules match simultaneously, the actions
🚱 L4 Proxy		
🐨 Security		-
🚍 Log Service		
Custom response pages		2
Multimedia Services		
Audio and Video Processing		
Image Processing	05 :: .	2

On the rule editing page, set the matching conditions that trigger this rule. Click Action > Select Box, and select
 Token Authentication in the pop-up action list.

4. In the Token Authentication operation, select "V" as the authentication method, enter your authentication key, and save the authentication key for use in subsequent steps.

IF 4	Comment			
Ν	Natching type ①	Operator	Value	
	HOST -	is in	×	
4	- And + Or			
A	Action 1	Method ①	Primary key (Required) ①	Backup key (optional) ①
	Token authentication	٧ -	3PXoBR23e0	
	ι			J
+ A	ction			
+ IF	:			

5. Finally, click **Save** to enable access control.

Step 3. Import the EdgeOne domain into VOD.

1. Log in to the VOD console and select Application Management on the left sidebar.

2. Select the target application. By default, you will enter the **Media Assets > Video Management > Uploaded** page.

3. Select Distribution and **Playback > Domain Name** on the left sidebar, click **Add Domain.**

4. On the Add Domain page, select **Import existing EdgeOne domain** as the domain type, then choose the EdgeOne domain added in step 1. Click **Confirm** to import the EdgeOne domain into Cloud VOD.



Domain Name Configuration			
Domain Type *		Import an existing EdgeOne domain	
EdgeOne Site *			*
EdgeOne Domain *			•
Confirm	Cancel		

Step 4. Add the Authentication Key to Cloud VOD (Optional)

Note :

If you have not enabled access control in EdgeOne, you can skip this step.

1. Log in to the VOD console and select Application Management on the left sidebar.

2. Select the target application. By default, you will enter the **Media Assets > Video Management > Uploaded** page.

3. Select Distribution and **Playback > Domain Name** on the left sidebar, select the EdgeOne domain you need to configure and click **Set**.

4. On the Domain Basic Configuration page, turn on the Authentication Key switch.

5. In the pop-up window, enter the authentication key saved in step 2 and click **Confirm.**

Notes

1. VOD currently only supports Type V authentication in EdgeOne.

2. If you modify the authentication key in EdgeOne, please promptly update the key in the domain settings of VOD to avoid any playback issues.

Related Documentation

If you want to learn more about VOD copyright protection, please refer to Media Encryption and Copyright Protection.



If you want to learn more about Type V in EdgeOne, please refer to Token Authentication.